## ETSITS 132 522 V10.5.0 (2013-07)



Digital cellular telecommunications system (Phase 2+); Universal Mobile Telecommunications System (UMTS); LTE;

Telecommunication management;
Self-Organizing Networks (SON)
Policy Network Resource Model (NRM)
Integration Reference Point (IRP);
Information Service (IS)
(3GPP TS 32.522 version 10.5.0 Release 10)



# Reference RTS/TSGS-0532522va50 Keywords GSM,LTE,UMTS

#### **ETSI**

650 Route des Lucioles F-06921 Sophia Antipolis Cedex - FRANCE

Tel.: +33 4 92 94 42 00 Fax: +33 4 93 65 47 16

Siret N° 348 623 562 00017 - NAF 742 C Association à but non lucratif enregistrée à la Sous-Préfecture de Grasse (06) N° 7803/88

#### Important notice

Individual copies of the present document can be downloaded from: <u>http://www.etsi.org</u>

The present document may be made available in more than one electronic version or in print. In any case of existing or perceived difference in contents between such versions, the reference version is the Portable Document Format (PDF). In case of dispute, the reference shall be the printing on ETSI printers of the PDF version kept on a specific network drive within ETSI Secretariat.

Users of the present document should be aware that the document may be subject to revision or change of status.

Information on the current status of this and other ETSI documents is available at

<a href="http://portal.etsi.org/tb/status/status.asp">http://portal.etsi.org/tb/status/status.asp</a></a>

#### **Copyright Notification**

No part may be reproduced except as authorized by written permission. The copyright and the foregoing restriction extend to reproduction in all media.

© European Telecommunications Standards Institute 2013. All rights reserved.

**DECT**<sup>TM</sup>, **PLUGTESTS**<sup>TM</sup>, **UMTS**<sup>TM</sup> and the ETSI logo are Trade Marks of ETSI registered for the benefit of its Members. **3GPP**<sup>TM</sup> and **LTE**<sup>TM</sup> are Trade Marks of ETSI registered for the benefit of its Members and of the 3GPP Organizational Partners.

GSM® and the GSM logo are Trade Marks registered and owned by the GSM Association.

## Intellectual Property Rights

IPRs essential or potentially essential to the present document may have been declared to ETSI. The information pertaining to these essential IPRs, if any, is publicly available for **ETSI members and non-members**, and can be found in ETSI SR 000 314: "Intellectual Property Rights (IPRs); Essential, or potentially Essential, IPRs notified to ETSI in respect of ETSI standards", which is available from the ETSI Secretariat. Latest updates are available on the ETSI Web server (http://ipr.etsi.org).

Pursuant to the ETSI IPR Policy, no investigation, including IPR searches, has been carried out by ETSI. No guarantee can be given as to the existence of other IPRs not referenced in ETSI SR 000 314 (or the updates on the ETSI Web server) which are, or may be, or may become, essential to the present document.

#### **Foreword**

This Technical Specification (TS) has been produced by ETSI 3rd Generation Partnership Project (3GPP).

The present document may refer to technical specifications or reports using their 3GPP identities, UMTS identities or GSM identities. These should be interpreted as being references to the corresponding ETSI deliverables.

The cross reference between GSM, UMTS, 3GPP and ETSI identities can be found under <a href="http://webapp.etsi.org/key/queryform.asp">http://webapp.etsi.org/key/queryform.asp</a>.

## Contents

Intelle	ectual Property Rights	2
Forew	vord	2
Forew	vord	5
Introd	luction	5
1	Scope	6
2	References	
3	Definitions and abbreviations	
3.1 3.2	Definitions	
3.2	Abbreviations	/
4	SON Policy and Optimization Function Definitions	8
4.1	Monitoring and Management Operations for Self-Optimization	
4.1.1	Monitoring and Management Function	
4.1.1.1	· · · · · · · · · · · · · · · · · · ·	
4.2	Load Balancing Optimization Function	
4.2.1	Objective and Targets	
4.2.2	Parameters To Be Optimized	
4.2.3	Optimization Method	
4.2.3.1		
4.2.3.2		
4.2.4	Architecture	
4.2.4.1		
4.2.4.2		
4.2.5	PM	
4.3	Handover (HO) Parameter Optimization Function	
4.3.1	Objective and Targets	
4.3.2	Parameters To Be Optimized	
4.3.3	Optimization Method	12
4.3.3.1	Problem Detection	12
4.3.3.2		
4.3.4	Architecture	12
4.3.4.1	Definition of Logical Functions	12
4.3.4.2		
4.3.5	PM	13
4.4	Interference Control Function	14
4.5	Capacity and Coverage Optimization Function	14
4.5.1	Objective and Targets	14
4.5.2	Parameters to be optimized	14
4.5.3	Optimization Method	14
4.5.3.1	Problem Detection	14
4.5.3.2	Problem Solution	15
4.5.4	Architecture	15
4.5.4.1	Definition of Logical Functions	15
4.5.4.2	2 Location of Logical Functions	15
4.6	RACH Optimization Function	16
4.6.1	Objective and Targets	16
4.6.2	Parameters to be optimized	
4.6.3	Optimization Method	17
4.6.3.1	Problem Detection	17
4.6.3.2	Problem Solution	17
4.6.4	PM	17
4.7	Optimization coordination	17
4.7.1	Introduction	
4.7.2	Coordination between SON functions below Itf-N and CM operations over itf-N	18

4.7.3	Coordination between different SON functions	18
4.7.3.1	Coordination between Cell Outage Compensation and Energy Saving Management	18
4.7.3.1.	1 Description	18
4.7.3.1.	Prevention	18
4.7.3.1.	3 Resolution	18
5	Information Object Classes (IOCs)	19
5.1	Information entities imported and local labels	
5.2	Class diagram	
5.2.1	Attributes and relationships	
5.2.2	Inheritance	
5.3	Information Object Class (IOC) definitions	22
5.3.1	SONT argets	22
5.3.1.1	Definition	
5.3.1.2	Attributes	22
5.3.1.3	Attribute constraints	22
5.3.1.4	Notifications	
5.3.2	SONControl	22
5.3.2.1	Definition	22
5.3.2.2	Attributes	23
5.3.2.3	Attribute constraints	
5.3.2.4	Notifications	23
5.3.3	ESPolicies	
5.3.3.1	Definition	
5.3.3.2	Attributes	
5.3.3.3	Attribute constraints	
5.3.3.4	Notifications	23
5.3.4	EUtranCellSON	24
5.3.4.1	Definition	24
5.3.4.2	Attributes	24
5.3.4.3	Attribute constraints	
5.3.4.4	Notifications	24
5.3.5	Void	24
5.4	Information relationship definitions	
5.5	Information attribute definitions	
5.5.1	Definition and legal values	
5.5.2	Constraints	
5.6	Common Notifications	
5.6.1	Configuration notifications	30
Annex	A (informative): Target Achievement Evaluation	31
Annex	B (informative): Change history	32
Histor	V.	33

## **Foreword**

This Technical Specification has been produced by the 3<sup>rd</sup> Generation Partnership Project (3GPP).

The contents of the present document are subject to continuing work within the TSG and may change following formal TSG approval. Should the TSG modify the contents of the present document, it will be re-released by the TSG with an identifying change of release date and an increase in version number as follows:

Version x.y.z

where:

- x the first digit:
  - 1 presented to TSG for information;
  - 2 presented to TSG for approval;
  - 3 or greater indicates TSG approved document under change control.

Point (IRP): Solution Set (SS) definitions

- y the second digit is incremented for all changes of substance, i.e. technical enhancements, corrections, updates, etc.
- z the third digit is incremented when editorial only changes have been incorporated in the document.

## Introduction

The present document is part of a TS-family covering the 3<sup>rd</sup> Generation Partnership Project Technical Specification Group Services and System Aspects, Telecommunication management; as identified below:

32.521:	Self-Organizing Networks (SON) Policy Network Resource Model (NRM) Integration Reference Point (IRP): Requirements
32.522:	Self-Organizing Networks (SON) Policy Network Resource Model (NRM) Integration Reference Point (IRP): Information Service (IS)
32.526:	Self-Organizing Networks (SON) Policy Network Resource Model (NRM) Integration Reference

## 1 Scope

The present document is part of an Integration Reference Point (IRP) named Self Organizing Networks (SON) Policy Network Resource Model (NRM) IRP, through which an IRPAgent can communicate management information to one or several IRPManagers concerning SON policies. The SON policy NRM IRP comprises a set of specifications defining Requirements, a protocol neutral Information Service and one or more Solution Set(s).

The present document specifies the protocol neutral SON policy NRM IRP: Information Service (IS).

In order to access the information defined by this NRM, an Interface IRP such as the "Basic CM IRP" is needed (3GPP TS 32.602 [11]). However, which Interface IRP is applicable is outside the scope of the present document.

The present document also contains stage 2 descriptions for those functionalities for the Self-Optimization OAM.

## 2 References

The following documents contain provisions which, through reference in this text, constitute provisions of the present document.

- References are either specific (identified by date of publication, edition number, version number, etc.) or non-specific.
- For a specific reference, subsequent revisions do not apply.
- For a non-specific reference, the latest version applies. In the case of a reference to a 3GPP document (including a GSM document), a non-specific reference implicitly refers to the latest version of that document *in the same Release as the present document*.

Release as th	ne present document.
[1]	3GPP TS 32.101: "Telecommunication management; Principles and high level requirements".
[2]	3GPP TS 32.102: "Telecommunication management; Architecture".
[3]	3GPP TS 32.150: "Telecommunication management; Integration Reference Point (IRP) Concept and definitions".
[4]	3GPP TR 21.905: "Vocabulary for 3GPP Specifications".
[5]	3GPP TS 32.521: "Telecommunication management; Self-Organizing Networks (SON) Policy Network Resource Model (NRM) Integration Reference Point (IRP): Requirements".
[6]	3GPP TS 36.331: "Technical Specification Group Radio Access Network; Evolved Universal Terrestrial Radio Access (E-UTRA); Radio Resource Control (RRC); Protocol specification".
[7]	3GPP TS 36.423: "Technical Specification Group Radio Access Network; Evolved Universal Terrestrial Radio Access Network (E-UTRAN); X2 Application Protocol (X2AP)".

- [8] 3GPP TS 32.425: "Technical Specification Group Services and System Aspects; Telecommunication management; Performance Management (PM); Performance measurements; Evolved Universal Terrestrial Radio Access Network (E-UTRAN)"
- [9] 3GPP TS 32.622: "Telecommunication management; Configuration Management (CM); Generic network resources Integration Reference Point (IRP): Network Resource Model (NRM)"
- [10] 3GPP TS 32.762: "Telecommunication management; Configuration Management (CM); Evolved Universal Terrestrial Radio Access Network (E-UTRAN) network resources Integration Reference Point (IRP): Network Resource Model (NRM)"
- [11] 3GPP TS 32.602: "Telecommunication management; Configuration Management (CM); Basic CM Integration Reference Point (IRP) Information Service (IS)".
- [12] 3GPP TS 36.413: "Technical Specification Group Radio Access Network; Evolved Universal Terrestrial Radio Access Network (E-UTRAN); S1 Application Protocol (S1AP)".

[13] 3GPP TS 36.314: "Evolved Universal Terrestrial Radio Access (E-UTRA); Layer 2 - Measurements".

[14] 3GPP TS 36.300: "Evolved Universal Terrestrial Radio Access (E-UTRA) and Evolved Universal

Terrestrial Radio Access Network (E-UTRAN); Overall description; Stage 2 ".

[15] 3GPP TS 37.320: "Universal Terrestrial Radio Access (UTRA) and Evolved Universal Terrestrial

Radio Access (E-UTRA); Radio measurement collection for Minimization of Drive Tests (MDT);

Overall description; Stage 2".

## 3 Definitions and abbreviations

#### 3.1 Definitions

For the purposes of the present document, the terms and definitions given in TS 32.101 [1], TS 32.102 [2], TS 32.150 [3] and TR 21.905 [4] and the following apply. A term defined in the present document takes precedence over the definition of the same term, if any, in TS 32.521 [5], TS 32.101 [1], TS 32.102 [2] and TR 21.905 [4], in that order.

Target: See 3GPP TS 32.521 [5].

Trigger condition: See 3GPP TS 32.521 [5].

**Hand-Over parameter Optimisation**: See clause 4.3 of this document and Mobility Robustness Optimisation (MRO) are synonyms (see TS 36.300 [14]).

#### 3.2 Abbreviations

For the purposes of the present document, the abbreviations given in TR 21.905 [4], TS 32.521 [5] and the following apply. An abbreviation defined in the present document takes precedence over the definition of the same abbreviation, if any, in TR 21.905 [4] and TS 32.521 [5].

CAC Composite Available Capacity
CDF Cumulative Distribution Function

EM Element Manager eNodeB, eNB evolved NodeB

E-UTRAN Evolved Universal Terrestrial Radio Access Network

HO Handover

HOO HandOver parameter Optimization ICIC Inter Cell Interference Coordination

IOC Information Object Class

LB Load Balancing

LBO Load Balancing Optimization
MRO Mobility Robustness Optimisation

NM Network Manager
NRM Network Resource Model

OAM Operation Administration Maintenance

RO RACH Optimization SON Self Organizing Networks

UE User Equipment

## 4 SON Policy and Optimization Function Definitions

# 4.1 Monitoring and Management Operations for Self-Optimization

## 4.1.1 Monitoring and Management Function

#### 4.1.1.1 Usage of Itf-N

For specifically defined Itf-N NRM Interface see clause 5.

## 4.2 Load Balancing Optimization Function

## 4.2.1 Objective and Targets

The objective of LB Optimization is to cope with undesired traffic load distribution and to minimize the number of handovers and redirections needed to achieve the load balancing. One of the following targets or the combination of the following targets shall be used. The specific target value or values shall be configured by operators. Operators should assign weights for targets being used.

Targets drawn from the following table can be configured for LBO:

Target Name	Definition	Legal Values
RRC connection	The number of Failed RRC connection establishments	Integer
establishments	related to load/ The total number of Attempted RRC	[0100] in unit
failure rate related to load	connection establishments.	percentage
load	The target is met if the actual rate is smaller than the target value.	
E-RAB setup failure	The number of E-RAB setup failure related to load/ The	Integer
rate related to load	total number of attempted E-RAB setup	[0100] in unit percentage
	For E-RAB setup failure related to load, the causes	
	'Reduce load in serving cell' and 'Radio resources not available' defined in TS 36.413 [12] could be used.	
	The target is met if the actual rate is smaller than the target value.	
RRC Connection	The number of abnormal RRC connection release related	Integer
Abnormal Release Rate Related to Load	to load/ The total number of RRC connection release.	[0100] in unit percentage
	The target is met if the actual rate is smaller than the target value.	
E-RAB Abnormal	The number of E-RAB abnormal release related to load/	Integer
Release Rate Related to Load	The total number of E-RAB release	[0100] in unit percentage
	For E-RAB setup failure related to load, the causes	
	'Reduce load in serving cell' and 'Radio resources not	
	available' defined in TS 36.413 [12] could be used.	
	The target is met if the actual rate is smaller than the	
	target value.	
Rate of failures	(the number of failure events related to handover) / (the	Integer
related to handover	total number of handover events)	[0100] in unit percentage
	The target is met if the actual rate is smaller than the target value.	
	larger value.	

For the following targets out of the above table, the target values depend on the composite available capacity range in the cell and are defined separately for uplink and downlink. For these tuples can be configured, indicating the capacity ranges together with the target value valid in that range.

RRC connection establishments failure rate related to load,

E-RAB setup failure rate related to load,

RRC Connection Abnormal Release Rate Related to Load,

E-RAB Abnormal Release Rate Related to Load

For the following targets shall be identical with the corresponding targets defined in Handover Optimization.

Rate of failures related to handover

#### 4.2.2 Parameters To Be Optimized

To reach load optimization target, LBO may optimize some mobility settings (HO and/or idle mobility configuration) defined in TS 36.331 [6].

## 4.2.3 Optimization Method

#### 4.2.3.1 Problem Detection

The problem detection is out of scope of this specification.

#### 4.2.3.2 Problem Solution

The problem solution is out of scope of this specification.


#### 4.2.4 Architecture

#### 4.2.4.1 Definition of Logical Functions

**LB Monitor Function:** This function is used for monitoring the load balance optimization (e.g. Monitoring related performance counters or alarms).

LB Policy control function: This function is used for configuring the load balance optimization policies.

## 4.2.4.2 Location of Logical Functions



For Load Balancing, the SON LB decision algorithm is located in eNB. The detailed SON functionalities in eNB are out of scope of this specification.

#### 4.2.5 PM

IRPManager may collect Load balancing related performance measurements. Performance Measurements related with Load balancing are captured in the table below:

Performance measurement name	Description	Related targets
The number of Failed RRC connection establishments related to load	Refer to 3GPP TS 32.425 [8] Failed RRC connection establishments	RRC connection establishments failure rate related to load
The total number of Attempted RRC connection establishments	Refer to 3GPP TS 32.425 [8] Attempted RRC connection establishments	RRC connection establishments failure rate related to load
The number of E-RAB setup failure related to load	Refer to 3GPP TS 32.425 [8] Number of initial SAE Bearers failed to setup	E-RAB setup failure rate related to load
The total number of attempted E-RAB setup	Refer to 3GPP TS 32.425 [8] Number of initial SAE Bearers attempted to setup	E-RAB setup failure rate related to load
The number of abnormal RRC connection release related to load	Number of UE CONTEXT Release Request initiated by eNodeB	RRC Connection Abnormal Release Rate Related to Load
The total number of RRC connection release	Number of Successful UE Context Release	RRC Connection Abnormal Release Rate Related to Load
The number of E-RAB abnormal release related to load	Refer to 3GPP TS 32.425 [8]  Number of SAE Bearers requested to release initiated by eNodeB per cause	E-RAB Abnormal Release Rate Related to Load
The total number of E-RAB release	Refer to 3GPP TS 32.425 [8] Number of SAE Bearers successfully released	E-RAB Abnormal Release Rate Related to Load
the number of failure events related to handover	Refer to 4.3.5	Rate of failures related to handover
the total number of handover events	Refer to 4.3.5	Rate of failures related to handover

NOTE: The monitoring of performance measurements will make use of existing PM IRP.

## 4.3 Handover (HO) Parameter Optimization Function

## 4.3.1 Objective and Targets

For intra-LTE, one of the following targets or the combination of the following targets shall be used. The specific target value shall be configured by operators. Operators should assign weights for targets being used.

Target Name	Definition	Legal Values
Rate of failures related to handover	(the number of failure events related to handover) / (the total number of handover events)	Integer [0100] in unit
Handover	Transcr of hardover events)	percentage
	The target is met if the actual rate is smaller than the target value.	

The objective of minimizing the number of unnecessary handovers shall always be pursued in case the other target/s configured by the operator is/are achieved. This objective may not need configuration of a target value.

## 4.3.2 Parameters To Be Optimized

The tables below summarise the handover parameters in TS 36.331 [6].

Table 4.3.2-1. Handover parameters that may be optimized for intra-frequency and inter-frequency handovers

Event	Summary	Tunable parameters	
A3	Neighbour becomes offset better than serving	Ofn, Ofs, Ocn, Ocs, Hys, Off, timeToTrigger	
A4	Neighbour becomes better than threshold	Ofn, Ocn, Hys, Thresh, Off, timeToTrigger	
A5	Serving becomes worse than threshold1 and	Ofn, Ocn, Hys, Thresh1, Thresh2, Off,	
	neighbour becomes better than threshold2	timeToTrigger	

Table 4.3.2-2. Handover parameters that may be optimised for inter RAT handover

Event	Summary	Tunable parameters
B1	Inter RAT Neighbour becomes better than threshold	Ofn, Hys, Thresh, timeToTrigger
B2	Serving becomes worse than threshold1 and inter RAT neighbour becomes better than threshold2	Ofn, Hys, Thresh1, Thresh2, timeToTrigger

#### 4.3.3 Optimization Method

#### 4.3.3.1 Problem Detection

HO Parameter Optimization Function shall focus on detecting the problem scenarios described in TS 32.521 [5]; namely: too early handovers, too late handovers and inefficient use of NW resources due to HOs. For more information about these scenarios see TS 32.521 [5] section 6.1.3.

The following inputs may be used for the identification of the problem scenarios:

- Event capture and analysis
- UE measurements
- Performance measurements

In event capture and analysis, the eNodeB exploits event information associated with a UE context, such as evidence of previous handovers (UE History, see TS 36.423 [7]) and HO failure details (such as in which cell the handover failed and where the UE re-established the connection).

UE measurements are sent within UE measurement reports and they may indicate whether HOs are too early or too late.

HO-related performance measurements (PMs) collected at the source and / or target eNB can be useful in detecting HO-related issues on the cell level. Since the impact of incorrect HO parameter setting will also be on the cell-level, PMs can provide useful information that can be used to detect and resolve HO-related issues due to incorrect parameter settings.

#### 4.3.3.2 Problem Solution

HO Parameter Optimization Function will aim at optimizing the HO parameters listed in Section 4.3.2 in such way to mitigate the problem scenarios discussed in Section 4.3.3.1. The optimization algorithms will not be specified. The exact set of HO parameters that may be adjusted by the algorithms is dictated by the choice of triggered HO measurements made by the RRM entity in an eNodeB.

#### 4.3.4 Architecture

#### 4.3.4.1 Definition of Logical Functions

**HO Parameter Optimization Monitor Function:** This function is used for monitoring the handover parameter optimization (e.g. monitoring related performance counters or alarms).

**HO Parameter Optimization Policy Control Function:** This function is used for configuring the handover parameter optimization policies.

#### 4.3.4.2 Location of Logical Functions

For HandOver (HO) parameter optimization there are several options for the location of the SON algorithm:

- 1. The SON algorithm is located in the eNB(s).
- 2. The SON algorithm is located in the EM, the parameter changes are executed in the eNBs.

An example for the first option is shown in figure 4.3.4.2:




Figure 4.3.4.2: Example when the SON algorithm is located in the eNB(s)

The detailed SON functionalities in eNB are out of scope of this specification.

#### 4.3.5 PM

IRPManager shall collect HO-related performance measurements from the source and / or target eNB which can be useful in detecting HO-related issues on the cell level. The following input can be used for the identification of the problem scenarios specified:

The number of RLF event happened within an interval after handover success.

Performance Measurements related to handover failure are captured in the table below.

The Performance Measurements are for outgoing handovers. Further, they should be available on a cell relation basis.

Performance measurement name	Description	Related targets
Number of handover events	Includes successful handovers plus all identified failures	Rate of failures related to handover
Number of HO failures	All failure cases	Rate of failures related to handover
Number of too early HO failures	Too early HO failure cases	Rate of failures related to handover
Number of too late HO failures	Too late HO failure cases	Rate of failures related to handover
Number of HO failures to wrong cell	HO failures to wrong cell	Rate of failures related to handover

NOTE: The monitoring of performance measurements will make use of existing PM IRP.

#### 4.4 Interference Control Function

## 4.5 Capacity and Coverage Optimization Function

#### 4.5.1 Objective and Targets

The objective of capacity and coverage optimization is to provide optimal coverage and capacity for the radio network. A tradeoff between capacity and coverage needs to be considered.

The detailed target(s) FFS.

## 4.5.2 Parameters to be optimized

To reach capacity and coverage optimization targets, the following parameters may be optimized:

- Downlink transmit power
- Antenna tilt
- Antenna azimuth

## 4.5.3 Optimization Method

#### 4.5.3.1 Problem Detection

The main symptoms of capacity and coverage optimization problems (see TS 37.320 [15]) are:

Coverage hole: A coverage hole is an area where the pilot signal strength is below a threshold which is required by a UE to access the network, or the SINRs of both serving and neighbor cells is below a level needed to maintain the basic service. Coverage holes are usually caused by physical obstructions such as new buildings, hills, or by unsuitable antenna parameters, or just inadequate RF planning. UE in coverage hole will suffer from call drop and radio link failure. Typical phenomenon of coverage hole is either HO failure happens frequently and cannot be optimized by HO parameter optimization or call drop happens frequently and cannot be rescued by RRC re-establishment.

**Weak coverage:** Weak coverage occurs when the pilot signal strength or the SNR (or SINR) of serving cell is below the level needed to maintain a planned performance requirement (e.g. cell edge bit-rate).

**Pilot pollution:** In areas where coverage of different cells overlap a lot, interference levels are high, power levels are high, energy consumption is high and cell performance may be low. Typically in this situation UEs may experience high SNR to more than one cell and high interference levels.

**Overshoot coverage:** Overshoot occurs when coverage of a cell reaches far beyond what is planned. It can occur as an 'island' of coverage in the interior of another cell, which may not be a direct neighbor. Reasons for overshoot may be reflections in buildings or across open water, lakes etc. UEs in this area may suffer call drops or high interference.

**DL** and **UL** channel coverage mismatch: DL channel coverage is larger than UL channel coverage is one typical scenario of DL and UL channel coverage mismatch. The UE will suffer UL problems when it moves into the mismatch area.

In a realistic network, these symptoms may be tolerated to a certain level. These symptoms may indicate a real problem when combined with other factors such as frequency of symptoms, duration of symptoms, or affected population.

The following inputs may be used for the identification of the problem scenarios:

- UE measurements
- Performance measurements
- Alarms, other monitoring information e.g. trace data

UE measurements are sent within UE measurement reports and they may indicate the capacity and coverage problem.

Capacity and coverage related performance measurements collected at the source and / or target eNB can be useful in detecting capacity and coverage related issues on the cell level. Minimizing Driver Test (MDT) or HO-related performance measurements may be used also in detecting capacity and coverage related issues on the cell level.

Alarms, other monitoring information e.g. trace data can be correlated to get an unambiguous indication of capacity and coverage problem.

#### 4.5.3.2 Problem Solution

Capacity and coverage optimization function will aim at optimizing the parameters listed in Section 4.5.2 in such way to mitigate the problem scenarios discussed in Section 4.5.3.1.

#### 4.5.4 Architecture

#### 4.5.4.1 Definition of Logical Functions

**CCO Monitor Function:** This function is used for monitoring the capacity and coverage optimization (e.g. monitoring related performance counters, UE measurements or alarms).

**CCO Policy Control Function:** This function is used for configuring the capacity and coverage optimization policies.

#### 4.5.4.2 Location of Logical Functions

For capacity and coverage optimization (CCO), there are several options for the location of the centralized CCO SON algorithm:

- 1. The CCO SON algorithm is located in the DM. The capacity and coverage optimization decision is made by the DM centralized CCO algorithm.
- 2. The CCO SON algorithm is located in the NM. The capacity and coverage optimization decision is made by the NM centralized CCO algorithm.

An example for the first option is shown in figure 4.5.4.2:




Figure 4.5.4.2: Example when the CCO SON algorithm is located in DM

The detailed CCO SON algorithm in OAM (NM centralized or EM centralized) is out of scope of this specification.

#### 4.5.5 PM

The IRPAgent shall support a capability allowing the IRPManager to collect CCO related performance measurements to know the situation of coverage or interference which may then trigger corresponding optimization procedures. Performance measurements related with CCO are captured in the table below:

Performance measurement	Description	Comment
name		
Maximum carrier transmit power	Refer to 3GPP TS 32.425 [8]	
·	Maximum value of the total carrier	
	power transmitted in a cell.	
Mean carrier transmit power	Refer to 3GPP TS 32.425 [8]	
	Mean value of the total carrier power	
	transmitted in a cell.	

## 4.6 RACH Optimization Function

## 4.6.1 Objective and Targets

The objective of RACH Optimization is to automatically set several parameters related to the performance of RACH. One of the following targets shall be used. The specific target value shall be configured by operators.

Target Name	Definition	Legal Values
Access Probability, AP	The probability that the UE has access after a certain random access attempt number.	CDF of access attempts. See section 5.5.1
	The target is met if the actual access probability is higher than the target probability value.	
Access Delay Probability, ADP	The probability distribution of Access Delay expected to be experienced by UEs accessing the RACH Channel.	CDF of delays. See section 5.5.1
	The target is met if the actual access probability is higher than the target probability value.	

## 4.6.2 Parameters to be optimized

To achieve RACH optimization target, RACH optimization function may optimize several parameters defined in TS 36.300 [14] section 22.4.3.

#### 4.6.3 Optimization Method

#### 4.6.3.1 Problem Detection

The problem detection is out of scope of this specification since the RACH optimization entity resides in the eNB.

#### 4.6.3.2 Problem Solution

The problem solution is out of scope of this specification since the RACH optimization entity resides in the eNB.

#### 4.6.4 PM

The IRPAgent shall support a capability allowing the IRPManager to collect RACH optimization related performance measurements. Performance measurements related with RACH optimization are captured in the table below:

Performance measurement	Description	Related targets
name		
Distribution of RACH preambles sent	Refer to 3GPP TS 32.425 [8] Cumulative Distribution of RACH preambles sent by UE	Access Probability, AP
Distribution of RACH access delay	Refer to 3GPP TS 32.425 [8] Cumulative Distribution of RACH Access Delay	Access Delay Probability, ADP

## 4.7 Optimization coordination

#### 4.7.1 Introduction

For coordination of SON Functions whose outputs are not standardized, the context of optimization coordination is:

1. IRPManager uses standardized capabilities to set the SON Function(s) targets, and where needed their weights.

Operators should assign weights for targets being used. The weights are used also for the evaluation of the targets. For details see Annex A.

For coordination of SON Functions whose outputs are standardized, the context of optimization coordination is FFS.

# 4.7.2 Coordination between SON functions below Itf-N and CM operations over itf-N

**FFS** 

#### 4.7.3 Coordination between different SON functions

Note: The coordination between different SON functions should be decided case by case.

## 4.7.3.1 Coordination between Cell Outage Compensation and Energy Saving Management

#### 4.7.3.1.1 Description

A conflict could arise between energy saving and cell outage compensation in the following scenario.

One or more candidate cells are configured to possibly take coverage of the original cell. The original cell is in energySaving state or is about to enter energySaving state. One or more candidate cells go into outage with the consequence that coverage of the original cell can not be provided any more.

#### 4.7.3.1.2 Prevention

Prevention is hardly possible, except making the cells as outage proof as possible. But cell outages can happen even to the most stable cell in a network.

#### 4.7.3.1.3 Resolution

If the original cell is in energySaving state, it shall leave energySaving state.

If the original cell is about to enter energySaving state, it shall not go into energySaving state until candidate cell outage is recovered and candidate cell is able to provide the coverage.

The original cell may go into the energySaving state after the candidate cell outage is recovered and coverage of the original cell can be taken over by candidate cell again.


## 5 Information Object Classes (IOCs)

## 5.1 Information entities imported and local labels

Label reference	Local label
3GPP TS 32.622 [9], IOC, Top	Тор
3GPP TS 32.622 [9], IOC, SubNetwork	SubNetwork
3GPP TS 32.762 [10], IOC, ENBFunction	ENBFunction
3GPP TS 32.762 [10], IOC, EUtranRelation	EUtranRelation
3GPP TS 32.762 [10], IOC, EUtranGenericCell	EUtranGenericCell

## 5.2 Class diagram

## 5.2.1 Attributes and relationships



NOTE 1: IOC SONControl shall be instantiated whenever one or more IOC SONTargets are instantiated.

Figure 5.2.1-1: Cell view of SON Policy NRM




Figure 5.2.1-2: ES Policies NRM IOCs (Containment Relationship)

NOTE 2: Also IOC SONControl is used for ES purposes – see clause 5.3.2.2 – but is not shown in Figure 5.2.1-2 to avoid the impression that there would an additional instance of this IOC be needed for ES.




Figure 5.2.1-3: IOCs to control SON on cell or E-UTRAN relation level (Containment Relationship)

## 5.2.2 Inheritance




Figure 5.2.2-1: SON Policy NRM Inheritance Hierarchy




Figure 5.2.2-2: ES Polices NRM IOCs (Inheritance Relationship)




Figure 5.2.2-3: Inheritance for IOC to control SON on cell level

## 5.3 Information Object Class (IOC) definitions

## 5.3.1 SONTargets

#### 5.3.1.1 Definition

This IOC represents targets for SON functions and their relative weights.

Target hierarchy rule:

An NRM IOC instance X may name-contain an IOC SONTargets instance T. The rule states that:

- If X name-contains a SONTargets instance T, then T is applicable to X.
- If X and all its superior instances do not name-contain any SONTargets instance, then no SONTargets instance is applicable to X.
- If X does not name-contain any SONTargets instance, but one or more of X"s superior instances name-contain a SONTargets instance, then the SONTargets instance of the superior instance closest to X, in X"s naming tree, is applicable to X.

#### 5.3.1.2 Attributes

Attribute name	Support Qualifier	Read Qualifier	Write Qualifier
hoFailureRate	O *)	М	М
rrcConnectionEstablishmentFailureRateCharacteristic	O *)	M	М
rrcConnectionAbnormalReleaseRateCharacteristic	O *)	M	М
eRabSetupFailureRateCharacteristic	O *)	М	М
eRabAbnormalReleaseRateCharacteristic	O *)	М	М
rachOptAccessProbability	CM **)	М	М
rachOptAccessDelayProbability	CM **)	M	M

<sup>\*)</sup> Note 1: At least one of the attributes shall be supported.

#### 5.3.1.3 Attribute constraints

Name	Definition
rachOptAccessProbability CM Support Qualifier	RACH Optimization is supported and Access Probability is supported as target.
rachOptAccessDelayProbability CM Support Qualifier	RACH Optimization is supported and Access Delay Probability is supported as target.

#### 5.3.1.4 Notifications

The common notifications defined in subclause 5.6.1 are valid for this IOC, without exceptions or additions.

#### 5.3.2 SONControl

#### 5.3.2.1 Definition

This IOC represents the possibility to switch on or off SON functions. This is provided for Handover optimization, Load Balancing optimization, Energy Saving and Cell Outage Compensation. For other SON functions like Coverage and Capacity optimization, RACH optimization etc. this is FFS.

<sup>\*\*)</sup> Note 2: Only one of these attributes shall be present.

#### 5.3.2.2 Attributes

Attribute name	Support Qualifier	Read Qualifier	Write Qualifier
hooSwitch	CM	M	M
lboSwitch	CM	M	M
esSwitch	CM	M	М
roSwitch	CM	M	M
cocSwitch	CM	M	M

#### 5.3.2.3 Attribute constraints

Name	Definition
hooSwitch CM Support Qualifier	Handover (HO) parameter Optimization function is supported.
lboSwitch CM Support Qualifier	Load Balancing Optimization function is supported.
esSwitch Support Qualifier	The condition is 'Distributed or EM-Centralized ESM architecture is supported'.
roSwitch CM Support Qualifier	RACH Optimization is supported.
cocSwitch Support Qualifier	The condition is 'CoC is supported'. Only allowed to be present, if SONControl is contained in subnetwork IOC instance.

#### 5.3.2.4 Notifications

The common notifications defined in subclause 5.6.1 are valid for this IOC, without exceptions or additions.

#### 5.3.3 ESPolicies

#### 5.3.3.1 Definition

This IOC represents the energy saving policies information. This object class is valid in a distributed ES architecture or in an EM-centralized ES architecture.

#### 5.3.3.2 Attributes

Attribute name	Support Qualifier	Read Qualifier	Write Qualifier
esActivationOriginalCellLoadParameters	CM	M	М
esActivationCandidateCellsLoadParameters	CM	М	М
esDeactivationCandidateCellsLoadParameters	CM	М	М

#### 5.3.3.3 Attribute constraints

Name	Definition
esActivationOriginalCellLoadParameters	The condition is "Intra-RAT ESM is supported AND the cell acts as an original cell".
esActivationCandidateCellsLoadParameters	The condition is "Intra-RAT ESM is supported AND the cell acts as a candidate cell".
esDeactivationCandidateCellsLoadParameters	The condition is "Intra-RAT ESM is supported AND the cell acts as a candidate cell".

#### 5.3.3.4 Notifications

The common notifications defined in subclause 5.6.1 are valid for this IOC, without exceptions or additions

## 5.3.4 EUtranCellSON

#### 5.3.4.1 Definition

This IOC represents the parameters for control of SON functions on E-UTRAN cell level.

#### 5.3.4.2 Attributes

Attribute name	Support Qualifier	Read Qualifier	Write Qualifier
maximumDeviationHoTrigger	CM	М	М
minimumTimeBetweenHoTriggerChange	CM	М	М

#### 5.3.4.3 Attribute constraints

Name	Definition
maximumDeviationHoTrigger Support Qualifier	The condition is "HOO function is supported".
minimumTimeBetweenHoTriggerChange Support Qualifier	The condition is "HOO function is supported".

#### 5.3.4.4 Notifications

The common notifications defined in subclause 5.6.1 are valid for this IOC, without exceptions or additions.

#### 5.3.5 Void

## 5.4 Information relationship definitions

None.

## 5.5 Information attribute definitions

## 5.5.1 Definition and legal values

Table 5.5.1.1 defines the attributes that are present in the Information Object Classes (IOCs) of the present document.

Table 5.5.1.1: Attributes definitions and legal values

Attribute Name	Definition	Legal Values
cocSwitch	This attribute allows the operator to enable/disable the COC functionality.	Enumerated {on, off}
eRabAbnormalRe leaseRateChara cteristic	The target is on the number of E-RAB abnormal release related to load divided by the total number of attempted E-RAB setups.	lowerEndOfCacRange and upperEndOfCacRange: Integer 010000
cteristic	of attempted E-RAB setups.  This attribute allows to define for a value the composite available capacity (CAC) range in which the target is valid. For this, it contains one characteristic dependent on Uplink CAC, one for Downlink CAC:  eRabAbnormalReleaseRateCharacteristicD ownlink and eRabAbnormalReleaseRateCharacteristicU plink.  At least one of these charateristics must be present. Together with the characteristic its targetWeight as a SON target is defined as part of this attribute. The characteristics have the following structure: eRabAbnormalReleaseRateCharacteristicD ownlink:  List of one or more entries, each consisting of: lowerEndOfCacRange, upperEndOfCacRange, eRabAbnormalReleaseRateCharacteristicU plink:  List of one or more entries, each consisting of: lowerEndOfCacRange, eRabAbnormalReleaseRateCharacteristicU plink:  List of one or more entries, each consisting of: lowerEndOfCacRange, eRabAbnormalReleaseRateTarget  eRabAbnormalReleaseRateTarget  Remark:  Formula for composite available capacity: Available Capacity = Cell Capacity Class Value * Capacity Value  For definition of Cell Capacity Class Value and Capacity Value see TS 36.331 [6]. These definitions lead to a value range of a composite available capacity from 010000. 36.423 [7] has cell capacity class value as optional parameter in case of intra-LTE load balancing. If cell capacity class value is not present, than 36.423 assumes that bandwidth should be used instead to assess the capacity.	Integer 01000  eRabAbnormalReleaseRateTarget: Integer 0100 (representing a percentage)  targetWeight: Integer 1N. The higher the number the higher the weight.
	This target is suitable for LBO.	

- D - l- G : : 3	The tennet is an the second of CE DAD 11 11	I
eRabSetupFailu	The target is on the number of E-RAB setup failures	lowerEndOfCacRange and
reRateCharacte	related to load divided by the total number of	upperEndOfCacRange and
ristic	attempted E-RAB setups.	targetWeight:
	For E-RAB setup failure related to load the causes	See
	'Reduce load in serving cell' and 'Radio resources	eRabAbnormalReleaseRateCharacterist
	not available' defined in TS 36.413 are used.	ic
	This attribute allows to define for a value the	
	composite available capacity (CAC) range in which	eRabSetUpFailureRateTarget:
	the target is valid. For this, it contains one	Integer 0100 (representing a
	characteristic dependent on Uplink CAC, one for	percentage)
	Downlink CAC:	
	eRabSetupFailureRateCharacteristicDown	
	link and	
	eRabSetupFailureRateCharacteristicUpli	
	nk.	
	At least one of these characteristics must be present.	
	Together with the characteristic its targetWeight as	
	a SON target is defined as part of this attribute.	
	The characteristics have the following structure:	
	eRabSetupFailureRateCharacteristicDown link:	
	List of one or more entries, each consisting of:	
	LowerEndOfCacRange,	
	UpperEndOfCacRange,	
	eRabSetUpFailureRateTarget	
	eRabSetupFailureRateCharacteristicUplink:	
	List of one or more entries, each consisting of:  LowerEndOfCacRange,	
	UpperEndOfCacRange,	
	eRabSetUpFailureRateTarget	
	For CAC see	
	eRabAbnormalReleaseRateCharacteristic	
	erababilornaliveleaservateorialiacteristic	
	This target is suitable for LBO.	
esActivationOr	This attributes is relevant, if the cell acts as an	Threshold: Integer 0100 (Percentage
iginalCellLoad	original cell.	of PRB usage, see 3GPP TS 36.314
Parameters	This attribute indicates the traffic load threshold and	[13])
Tarameters	the time duration, which are used by distributed ES	TimeDuration: Integer (in unit of
	algorithms to allow a cell to enter the energySaving	seconds)
	state. The time duration indicates how long the load	
	needs to have been below the threshold.	
esActivationCa	This attributes is relevant, if the cell acts as a	Threshold: Integer 0100 (Percentage
ndidateCellsLo	candidate cell.	of PRB usage (see 3GPP TS 36.314
adParameters	This attribute indicates the traffic load threshold and	[13]))
	the time duration, which are used by distributed ES	TimeDuration: Integer (in unit of
	algorithms level to allow a n "original" cell to enter	seconds)
	the energySaving state. Threshold and duration are	
	applied to the candidate cell(s) which will provides	
	coverage backup of an original cell when it is in the	
	energySaving state. The threshold applies in the	
	same way for a candidate cell, no matter for which	
	original cell it will provide backup coverage.	
	The time duration indicates how long the traffic in	
	the candidate cell needs to have been below the	
	threshold before any original cell which will be	
	provided backup coverage by the candidate cell	
	enters energy saving state.	
L		1

EsDeactivation CandidateCells LoadParameters  This attributes is relevant, if the cell acts as a candidate cell. This attribute indicates the traffic load threshold and the time duration which is used by distributed ES algorithms to allow a cell to leave the energySaving state. Threshold and time duration are applied to the candidate cell when it which provides coverage backup for the cell in energySaving state. The threshold applies in the same way for a candidate cell, no matter for which original cell it provides backup coverage. The time duration indicates how long the traffic in the candidate cell needs to have been above the threshold to wake up one or more original cells which have been provided backup coverage by the candidate cell.  esSwitch  This attribute determines whether the energy saving function is enabled or disabled.  This indicates the assigned HOO target of the number of failure events related to handover divided by the total number of handover events, together with its targetWeight.  This target is suitable for HOO or LBO.  This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This parameter allows the IRPManager to define the maximum Beloved absolute deviation of the cell pair.  This parameter allows the IRPManager to define the maximum allowed absolute deviation of the cell pair.  This parameter allows the IRPManager to define the maximum allowed absolute deviation of the cell pair.	D + + - '	This stall was in male and if the soull note	Thursday Internation 400 (Dame 1
This attribute indicates the traffic load threshold and the time duration which is used by distributed ES algorithms to allow a cell to leave the energySaving state. Threshold and time duration are applied to the candidate cell when it which provides coverage backup for the cell in energySaving state. The threshold applies in the same way for a candidate cell, no matter for which original cell it provides backup coverage.  The time duration indicates how long the traffic in the candidate cell needs to have been above the threshold to wake up one or more original cells which have been provided backup coverage by the candidate cell.  ESSwitch  This attribute determines whether the energy saving function is enabled or disabled.  This indicates the assigned HOO target of the number of failure events related to handover divided by the total number of handover events, together with its targetWeight.  This target is suitable for HOO or LBO.  This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  This parameter allows the IRPManager to define the Integer (+1+96)		· · · · · · · · · · · · · · · · · · ·	
and the time duration which is used by distributed ES algorithms to allow a cell to leave the energySaving state. Threshold and time duration are applied to the candidate cell when it which provides coverage backup for the cell in energySaving state. The threshold applies in the same way for a candidate cell, no matter for which original cell it provides backup coverage.  The time duration indicates how long the traffic in the candidate cell needs to have been above the threshold to wake up one or more original cells which have been provided backup coverage by the candidate cell.  ESSwitch  This attribute determines whether the energy saving function is enabled or disabled.  hoFailureRate  This indicates the assigned HOO target of the number of failure events related to handover divided by the total number of handover events, together with its targetWeight.  This target is suitable for HOO or LBO.  This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  This parameter allows the IRPManager to define the Integer (in unit of seconds)  TimeDuration: Integer (in unit of seconds)			•
ES algorithms to allow a cell to leave the energySaving state. Threshold and time duration are applied to the candidate cell when it which provides coverage backup for the cell in energySaving state. The threshold applies in the same way for a candidate cell, no matter for which original cell it provides backup coverage.  The time duration indicates how long the traffic in the candidate cell needs to have been above the threshold to wake up one or more original cells which have been provided backup coverage by the candidate cell.  ESSWitch  This attribute determines whether the energy saving function is enabled or disabled.  This indicates the assigned HOO target of the number of failure events related to handover divided by the total number of handover events, together with its targetWeight.  This target is suitable for HOO or LBO.  This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  This parameter allows the IRPManager to define the Integer (+1+96)	LoadParameters		
energySaving state. Threshold and time duration are applied to the candidate cell when it which provides coverage backup for the cell in energySaving state. The threshold applies in the same way for a candidate cell, no matter for which original cell it provides backup coverage.  The time duration indicates how long the traffic in the candidate cell needs to have been above the threshold to wake up one or more original cells which have been provided backup coverage by the candidate cell.  esSwitch  This attribute determines whether the energy saving function is enabled or disabled.  hoFailureRate  This indicates the assigned HOO target of the number of failure events related to handover divided by the total number of handover events, together with its targetWeight.  This target is suitable for HOO or LBO.  hooSwitch  This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  This parameter allows the IRPManager to define the Integer (+1+96)		and the time duration which is used by distributed	TimeDuration: Integer (in unit of
are applied to the candidate cell when it which provides coverage backup for the cell in energySaving state. The threshold applies in the same way for a candidate cell, no matter for which original cell it provides backup coverage.  The time duration indicates how long the traffic in the candidate cell needs to have been above the threshold to wake up one or more original cells which have been provided backup coverage by the candidate cell.  esSwitch  This attribute determines whether the energy saving function is enabled or disabled.  This indicates the assigned HOO target of the number of failure events related to handover divided by the total number of handover events, together with its targetWeight.  This target is suitable for HOO or LBO.  hooSwitch  This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  This parameter allows the IRPManager to define the Integer (+1+96)		ES algorithms to allow a cell to leave the	seconds)
are applied to the candidate cell when it which provides coverage backup for the cell in energySaving state. The threshold applies in the same way for a candidate cell, no matter for which original cell it provides backup coverage.  The time duration indicates how long the traffic in the candidate cell needs to have been above the threshold to wake up one or more original cells which have been provided backup coverage by the candidate cell.  esSwitch  This attribute determines whether the energy saving function is enabled or disabled.  This indicates the assigned HOO target of the number of failure events related to handover divided by the total number of handover events, together with its targetWeight.  This target is suitable for HOO or LBO.  hooSwitch  This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  This parameter allows the IRPManager to define the Integer (+1+96)		energySaving state. Threshold and time duration	
energySaving state. The threshold applies in the same way for a candidate cell, no matter for which original cell it provides backup coverage.  The time duration indicates how long the traffic in the candidate cell needs to have been above the threshold to wake up one or more original cells which have been provided backup coverage by the candidate cell.  ESSWitch  This attribute determines whether the energy saving function is enabled or disabled.  This indicates the assigned HOO target of the number of failure events related to handover divided by the total number of handover events, together with its targetWeight.  This target is suitable for HOO or LBO.  This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  This parameter allows the IRPManager to define the Integer (+1+96)		are applied to the candidate cell when it which	
energySaving state. The threshold applies in the same way for a candidate cell, no matter for which original cell it provides backup coverage.  The time duration indicates how long the traffic in the candidate cell needs to have been above the threshold to wake up one or more original cells which have been provided backup coverage by the candidate cell.  ESSWitch  This attribute determines whether the energy saving function is enabled or disabled.  This indicates the assigned HOO target of the number of failure events related to handover divided by the total number of handover events, together with its targetWeight.  This target is suitable for HOO or LBO.  This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  This parameter allows the IRPManager to define the Integer (+1+96)		provides coverage backup for the cell in	
same way for a candidate cell, no matter for which original cell it provides backup coverage.  The time duration indicates how long the traffic in the candidate cell needs to have been above the threshold to wake up one or more original cells which have been provided backup coverage by the candidate cell.  esSwitch  This attribute determines whether the energy saving function is enabled or disabled.  hoFailureRate  This indicates the assigned HOO target of the number of failure events related to handover divided by the total number of handover events, together with its targetWeight.  This target is suitable for HOO or LBO.  hooSwitch  This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  maximumDeviati  This parameter allows the IRPManager to define the Integer (+1+96)			
original cell it provides backup coverage. The time duration indicates how long the traffic in the candidate cell needs to have been above the threshold to wake up one or more original cells which have been provided backup coverage by the candidate cell.  esSwitch This attribute determines whether the energy saving function is enabled or disabled.  hoFailureRate This indicates the assigned HOO target of the number of failure events related to handover divided by the total number of handover events, together with its targetWeight.  This target is suitable for HOO or LBO.  hooSwitch This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  maximumDeviati This parameter allows the IRPManager to define the Integer (+1+96)			
The time duration indicates how long the traffic in the candidate cell needs to have been above the threshold to wake up one or more original cells which have been provided backup coverage by the candidate cell.  esSwitch  This attribute determines whether the energy saving function is enabled or disabled.  hoFailureRate  This indicates the assigned HOO target of the number of failure events related to handover divided by the total number of handover events, together with its targetWeight.  This target is suitable for HOO or LBO.  hooSwitch  This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  maximumDeviati  This parameter allows the IRPManager to define the  Integer (+1+96)			
the candidate cell needs to have been above the threshold to wake up one or more original cells which have been provided backup coverage by the candidate cell.  esSwitch  This attribute determines whether the energy saving function is enabled or disabled.  hoFailureRate  This indicates the assigned HOO target of the number of failure events related to handover divided by the total number of handover events, together with its targetWeight.  This target is suitable for HOO or LBO.  hooSwitch  This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  maximumDeviati  This parameter allows the IRPManager to define the Integer (+1+96)			
threshold to wake up one or more original cells which have been provided backup coverage by the candidate cell.  esSwitch This attribute determines whether the energy saving function is enabled or disabled.  hoFailureRate This indicates the assigned HOO target of the number of failure events related to handover divided by the total number of handover events, together with its targetWeight.  This target is suitable for HOO or LBO.  hooSwitch This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  This parameter allows the IRPManager to define the  Integer (+1+96)			
which have been provided backup coverage by the candidate cell.  esSwitch This attribute determines whether the energy saving function is enabled or disabled.  hoFailureRate This indicates the assigned HOO target of the number of failure events related to handover divided by the total number of handover events, together with its targetWeight.  This target is suitable for HOO or LBO.  hooSwitch This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  IboSwitch This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  maximumDeviati This parameter allows the IRPManager to define the  On, off Integer (+1+96)			
candidate cell.  Passwitch  This attribute determines whether the energy saving function is enabled or disabled.  This indicates the assigned HOO target of the number of failure events related to handover divided by the total number of handover events, together with its targetWeight.  This target is suitable for HOO or LBO.  This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  This parameter allows the IRPManager to define the Integer (+1+96)			
This attribute determines whether the energy saving function is enabled or disabled.  This indicates the assigned HOO target of the number of failure events related to handover divided by the total number of handover events, together with its targetWeight.  This target is suitable for HOO or LBO.  This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  This parameter allows the IRPManager to define the Integer (+1+96)			
function is enabled or disabled.  This indicates the assigned HOO target of the number of failure events related to handover divided by the total number of handover events, together with its targetWeight.  This target is suitable for HOO or LBO.  This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  This parameter allows the IRPManager to define the Integer (+1+96)			2 "
hoFailureRate This indicates the assigned HOO target of the number of failure events related to handover divided by the total number of handover events, together with its targetWeight.  This target is suitable for HOO or LBO. This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  This parameter allows the IRPManager to define the  This parameter (+1+96)	esswitch		On, off
number of failure events related to handover divided by the total number of handover events, together with its targetWeight.  This target is suitable for HOO or LBO.  This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  This parameter allows the IRPManager to define the Integer (+1+96)			
by the total number of handover events, together with its targetWeight.  This target is suitable for HOO or LBO.  This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  This parameter allows the IRPManager to define the Integer (+1+96)	hoFailureRate		
with its targetWeight.  This target is suitable for HOO or LBO.  This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  This parameter allows the IRPManager to define the Integer (+1+96)			
This target is suitable for HOO or LBO.  This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  This parameter allows the IRPManager to define the Integer (+1+96)			
This target is suitable for HOO or LBO.  hooSwitch This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  lboSwitch This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  maximumDeviati This parameter allows the IRPManager to define the Integer (+1+96)		with its targetWeight.	
hooSwitch This attribute determines whether the Handover parameter Optimization Function is activated or deactivated.  1boSwitch This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  maximumDeviati This parameter allows the IRPManager to define the Integer (+1+96)			ic).
parameter Optimization Function is activated or deactivated.  1boSwitch This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  maximumDeviati This parameter allows the IRPManager to define the Integer (+1+96)			
deactivated.  This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  This parameter allows the IRPManager to define the Integer (+1+96)	hooSwitch	This attribute determines whether the Handover	On, off
1boSwitch This attribute determines whether the Load Balancing Optimization Function is activated or deactivated.  maximumDeviati This parameter allows the IRPManager to define the Integer (+1+96)		parameter Optimization Function is activated or	
Balancing Optimization Function is activated or deactivated.  maximumDeviati This parameter allows the IRPManager to define the Integer (+1+96)		deactivated.	
deactivated.  maximumDeviati This parameter allows the IRPManager to define the Integer (+1+96)	lboSwitch	This attribute determines whether the Load	On, off
deactivated.  maximumDeviati This parameter allows the IRPManager to define the Integer (+1+96)		Balancing Optimization Function is activated or	
The parameter and its manager to define the manager (* 111.00)			
	maximumDeviati	This parameter allows the IRPManager to define the	Integer (+1+96)
1 Seement and the contract of	onHoTrigger	maximum allowed absolute deviation of the cell pair	Unit: 0.5 dB
specific part of Handover Trigger (as defined in [14]		I	
(§22.4.1.4), from the default point of operation.			
minimumTimeBet This parameter defines the minimum allowed time Integer (01440)	minimumTimeBet		Integer (01440)
weenHoTriggerC interval between two changes of the Handover Unit: Minutes	weenHoTriggerC		
hange Trigger performed by MRO.	hange	I ~	

rachOptAccessD elayProbabilit Y	This is a list of target Access Delay probability ( <i>AD<sub>P</sub></i> ) for the RACH optimization function.  Each instance <i>AD<sub>P</sub></i> of the list is the target time before the UE gets access on the random access channel, for the <i>P</i> percent of the successful RACH Access attempts with lowest access delay, over an unspecified sampling period.  This target is suitable for RO.	Each element of the list, $AD_{Pn}$ , is a pair $(a, b)$ where $a$ is the targetProbability (in %) and $b$ is the access delay (in milliseconds).  The legal values for $a$ are 25, 50, 75, 90.  The legal values for $b$ are 10 to 560.  If $AD_{Px}$ "s $a$ is larger than that of $AD_{Py}$ , then $AD_{Px}$ "s $b$ must be larger than that of $AD_{Py}$ .
		The number of elements specified is 4. The number of elements supported is vendor specific. The choice of supported values for <i>a</i> and <i>b</i> is vendor-specific.
rachOptAccessP robability	This is a list of target Access Probability $(AP_n)$ for the RACH optimization function.  Each instance $AP_n$ of the list is the probability that the UE gets access on the random access channel within $n$ number of attempts, over an unspecified sampling period.  This target is suitable for RO.	Each element of the list, $AP_n$ , is a pair $(a, n)$ where $a$ is the targetProbability (in %) and $n$ is the access attempt number.  The legal values for $a$ are 25, 50, 75, 90.  The legal values for $n$ are 1 to 200.  If $AP_x$ "s $a$ is larger than that of $AP_y$ , then $AP_x$ "s $n$ must be larger than that of $AP_y$ .  The number of elements specified is 4. The number of elements supported is vendor specific. The choice of supported values for $a$ and $a$ is vendor-specific.
roSwitch	This attribute determines whether the RACH Optimization function is activated or deactivated.	On, off

rrcConnectionA The target is on the number of abnormal RRC lowerEndOfCacRange and bnormalRelease connection releases related to load divided by the upperEndOfCacRange and RateCharacteri total number of RRC connection releases. targetWeight: stic See This attribute allows to define for a value the eRabAbnormalReleaseRateCharacterist composite available capacity (CAC) range in which the target is valid. For this, it contains one characteristic dependent on Uplink CAC, one for rrc Connection Abnormal Release Rate TarDownlink CAC: rrcConnectionAbnormalReleaseRateCharac Integer 0..100 (representing a teristicDownlink and percentage) rrcConnectionAbnormalReleaseRateCharac teristicUplink. At least one of these charateristics must be present. Together with the characteristic its targetWeight as a SON target is defined as part of this attribute. The characteristics have the following structure: rrcConnectionAbnormalReleaseRateCharac teristicDownlink: List of one or more entries, each consisting of: lowerEndOfCacRange, upperEndOfCacRange, rrcConnectionAbnormalReleaseRateTarget rrcConnectionAbnormalReleaseCharacteri sticUplink: List of one or more entries, each consisting of: lowerEndOfCacRange, upperEndOfCacRange, rrcConnectionAbnormalReleaseRateTarget For CAC see eRabAbnormalReleaseRateCharacteristic This target is suitable for LBO. rrcConnectionE The target is on the number of RRC connection lowerEndOfCacRange and stablishmentFa establishment failures related to load divided by the upperEndOfCacRange and ilureRateChara total number of attempted RRC connection targetWeigth: cteristic establishments. eRabAbnormalReleaseRateCharacterist This attribute allows to define for a value the composite available capacity (CAC) range in which the target is valid. For this, it contains one rrcConnectionEstablishmentFailureRate characteristic dependent on Uplink CAC, one for Target: Downlink CAC: Integer 0..100 (representing a rrcConnectionEstablishmentFailureRateC percentage) haracteristicDownlink and rrcConnectionEstablishmentFailureRateC haracteristicUplink. At least one of these charateristics must be present. Together with the characteristic its targetWeigth as a SON target is defined as part of this attribute. The characteristics have the following structure: rrcConnectionEstablishmentFailureRateC haracteristicDownlink: List of one or more entries, each consisting of: lowerEndOfCacRange, upperEndOfCacRange. rrcConnectionEstablishmentFailureRateTarget rrcConnectionEstablishmentFailureRateC haracteristicUplink: List of one or more entries, each consisting of: lowerEndOfCacRange, upperEndOfCacRange, rrcConnectionEstablishmentFailureRateTarget

For CAC see

eRabAbnormalReleaseRateCharacteristic

This target is suitable for LBO.

## 5.5.2 Constraints

None.

## 5.6 Common Notifications

## 5.6.1 Configuration notifications

Name	Qualifier	Notes
notifyAttributeValueChange	0	
notifyObjectCreation	0	
notifyObjectDeletion	0	

# Annex A (informative): Target Achievement Evaluation

To evaluate the result of the optimization the target achievement needs to be evaluated. This can be done by calculating the Total Target Achievement as follows.

The Total Target Achievement is the sum of the products of the individual target achievement (difference between target and performance) and the individual targetWeights:

```
\begin{split} Total \ Target \ Achievement = \\ Sum_{\ i=1..n} \ [ \ ( \ minTarget_{\ i} - performance_{\ i} \ ) \ x \ weight_{i} ] \\ + Sum_{\ j=1..n} \ [ \ performance_{\ j} \ - maxTarget_{\ j} \ ) \ x \ weight_{\ j} \ ] \end{split}
```

where minTarget is a target to be minimized and maxTarget is a target to be maximized.

For targets with a substructure (like \*Characteristic, see §5.5.1) the above formula is applied to each individual substructure target.

The higher the Total Target Achievement, the better is the result of the optimization.

# Annex B (informative): Change history

Change history							
Date	TSG #	TSG Doc.	CR	Rev	Subject/Comment	Old	New
2010-03	SA#47	SP-100053	<b> </b>		Presentation to SA for Information and Approval		1.0.0
2010-03					Publication of SA approved version	1.0.0	9.0.0
2010-09	SA#49	SP-100491	001		Remove targets based on not supported by measurements	9.0.0	9.1.0
2010-12	SA#50	SP-100858	003	1	Correcting the support qualifiers of SONControl attributes	9.1.0	9.2.0
2010-12	SA#50	SP-100749	005	-	Disambiguate and correct the description of SON Targets hierarchy	9.1.0	9.2.0
2010-12	SA#50	SP-100833	002	3	Allow EM centralized architecture for Hand-over parameter optimization - Align with 32.500	9.2.0	10.0.0
2010-12	SA#50	SP-100866	004	3	Adding NRM for Energy Saving Management policies and ESM switch	9.2.0	10.0.0
2011-01				-	Correction of misimplementation of CR in clause 5.3.2.3 and CR history correction.	10.0.0	10.0.1
2011-03	SA#51	SP-110098	10	2	Introducing RACH optimization management	10.0.1	10.1.0
2011-03	SA#51	SP-110098	11	-	Rapporteur clean-up for editorial errors	10.0.1	10.1.0
2011-03	SA#51	SP-110100	13	3	Use ESPolicies also for EM centralized architecture	10.0.1	10.1.0
2011-03	SA#51	SP-110100	14	-	Correct cardinality of ESPolicies	10.0.1	10.1.0
2011-03	SA#51	SP-110097	16	_	Add a new attribute into SONControl object class to switch on/off Cell Outage Compensation - Align with 32.541	10.0.1	10.1.0
2011-06	SA#52	SP-110284	18	1	Finalization of Rel-10 SON functionalities	10.1.0	10.2.0
2011-06	SA#52	SP-110284	66	2	Add parameters to control Mobility Robustness Optimization	10.1.0	10.2.0
2011-12	SA#54	SP-110721	70	1	Correction MRO management of HO Trigger	10.2.0	10.3.0
2012-09	SA#57	SP-120558	97	2	Correct candidateCellLoadParameters	10.3.0	10.4.0
2013-03					Editorial correction on the ToC and subclause headers (MCC)	10.4.0	10.4.1
2013-03					Editorial correction of the title of the spec	10.4.1	10.4.2
2013-06	SA#60	SP-130266	137	-	Remove EUtranRelationSON in UML diagram	10.4.2 10.5	10.5.0
		138 SA#60	A#0U   SP-130200	-	Correction of attribute constraints	10.4.2	10.5.0

## History

Document history				
V10.1.0	May 2011	Publication		
V10.2.0	June 2011	Publication		
V10.3.0	January 2012	Publication		
V10.4.0	September 2012	Publication		
V10.4.2	April 2013	Publication		
V10.5.0	July 2013	Publication		