


# ETSI TS 129 198 V3.0.0 (2000-06)

*Technical Specification*

**Universal Mobile Telecommunications System (UMTS);  
Open Service Architecture Application  
Programming Interface - Part 1  
(3G TS 29.198 version 3.0.0 Release 1999)**



---

Reference

DTS/TSGN-0529198U

---

Keywords

UMTS

***ETSI***

---

650 Route des Lucioles  
F-06921 Sophia Antipolis Cedex - FRANCE

Tel.: +33 4 92 94 42 00 Fax: +33 4 93 65 47 16

Siret N° 348 623 562 00017 - NAF 742 C  
Association à but non lucratif enregistrée à la  
Sous-Préfecture de Grasse (06) N° 7803/88

---

***Important notice***

Individual copies of the present document can be downloaded from:  
<http://www.etsi.org>

The present document may be made available in more than one electronic version or in print. In any case of existing or perceived difference in contents between such versions, the reference version is the Portable Document Format (PDF). In case of dispute, the reference shall be the printing on ETSI printers of the PDF version kept on a specific network drive within ETSI Secretariat.

Users of the present document should be aware that the document may be subject to revision or change of status.  
Information on the current status of this and other ETSI documents is available at <http://www.etsi.org/tb/status/>

If you find errors in the present document, send your comment to:  
[editor@etsi.fr](mailto:editor@etsi.fr)

---

***Copyright Notification***

No part may be reproduced except as authorized by written permission.  
The copyright and the foregoing restriction extend to reproduction in all media.

© European Telecommunications Standards Institute 2000.

All rights reserved.

---

## Intellectual Property Rights

IPRs essential or potentially essential to the present document may have been declared to ETSI. The information pertaining to these essential IPRs, if any, is publicly available for **ETSI members and non-members**, and can be found in ETSI SR 000 314: "*Intellectual Property Rights (IPRs); Essential, or potentially Essential, IPRs notified to ETSI in respect of ETSI standards*", which is available from the ETSI Secretariat. Latest updates are available on the ETSI Web server (<http://www.etsi.org/ipr>).

Pursuant to the ETSI IPR Policy, no investigation, including IPR searches, has been carried out by ETSI. No guarantee can be given as to the existence of other IPRs not referenced in ETSI SR 000 314 (or the updates on the ETSI Web server) which are, or may be, or may become, essential to the present document.

---

## Foreword

This Technical Specification (TS) has been produced by the ETSI 3<sup>rd</sup> Generation Partnership Project (3GPP).

The present document may refer to technical specifications or reports using their 3GPP identities, UMTS identities or GSM identities. These should be interpreted as being references to the corresponding ETSI deliverables.

The cross reference between GSM, UMTS, 3GPP and ETSI identities can be found under [www.etsi.org/key](http://www.etsi.org/key).

---

## Contents

Foreword.....	10
1 Scope .....	10
2 References .....	11
3 Definitions and abbreviations.....	12
3.1 Definitions.....	12
3.2 Abbreviations.....	13
4 Open Service Architecture .....	14
5 Methodology .....	15
5.1 Tools and Languages .....	15
5.2 Packaging.....	15
5.3 Colours.....	15
5.4 Naming scheme.....	15
5.5 Error results.....	16
5.6 References.....	16
5.7 Number of out parameters.....	16
5.8 Strings and Collections .....	17
5.9 Prefixes .....	17
5.10 Naming space across CORBA modules .....	17
6 Class diagrams.....	19
6.1 Class diagrams common across OSA.....	19
6.1.1 Base OSA interface .....	19
6.1.2 Generic Service Capability Feature interface .....	19
6.2 Class diagrams for the Framework.....	20
6.2.1 Top level Framework packages.....	20
6.2.2 Service Discovery.....	21
6.2.3 Trust and Security Management.....	22
6.2.3.1 IpInitial .....	23
6.2.3.2 IpAppAuthentication .....	23
6.2.3.3 IpAuthentication.....	23
6.2.3.4 IpAccess .....	24
6.2.3.5 IpAppAccess .....	24
6.2.4 Integrity Management .....	25
6.2.4.1 IpHeartBeatMgmt.....	25
6.2.4.2 IpAppHeartBeatMgmt.....	25
6.2.4.3 IpHeartBeat .....	26
6.2.4.4 IpAppHeartBeat .....	26
6.2.4.5 IpLoadManager .....	26
6.2.4.6 IpAppLoadManager .....	27
6.2.4.7 IpFaultManager .....	27
6.2.4.8 IpAppFaultManager .....	27
6.2.4.9 IpOAM .....	28
6.2.4.10 IpAppOAM.....	28
6.2.5 Service Registration .....	28
6.2.6 Service Factory.....	29
6.3 Generic Call Control .....	29
6.3.1 Interface Classes.....	31
6.3.1.1 IpAppCallControlManager .....	31
6.3.1.2 IpCallControlManager.....	31
6.3.1.3 IpAppCall .....	31
6.3.1.4 IpCall .....	32
6.4 Generic User Interaction and Call User Interaction .....	32
6.4.1 Relation between IpCall and IpUICall during call related user interaction.....	33
6.4.2 Interface Classes.....	34

6.4.2.1	IpAppUIManager .....	34
6.4.2.2	IpUIManager .....	34
6.4.2.3	IpAppUI .....	35
6.4.2.4	IpUI .....	36
6.4.2.5	IpAppUICall .....	36
6.4.2.6	IpUICall .....	36
6.5	Data Session Control .....	37
6.5.1	Interface Classes .....	38
6.5.1.1	IpAppDataSessionControlManager .....	38
6.5.1.2	IpDataSessionControlManager .....	39
6.5.1.3	IpAppDataSession .....	39
6.5.1.4	IpDataSession .....	40
6.6	Network User Location .....	41
6.6.1	Network User Location SCF interface .....	41
6.6.2	Network User Location application interface .....	42
6.7	User Status .....	42
6.7.1	User Status SCF interface .....	43
6.7.2	User Status application interface .....	43
6.8	Terminal Capabilities .....	43
6.8.1	Terminal Capabilities SCF interface .....	44
7	State Transition Diagrams .....	45
7.1	Framework .....	45
7.1.1	IpAuthentication .....	45
7.1.1.1	Idle state .....	45
7.1.1.2	Init Authentication state .....	46
7.1.1.3	Wait For Application Result state .....	46
7.1.1.4	Application Authenticated state .....	46
7.1.2	IpAccess .....	46
7.1.2.1	Active state .....	46
7.1.3	IpServiceDiscovery .....	47
7.1.3.1	Active state .....	47
7.1.4	IpLoadManager .....	48
7.1.4.1	Idle State .....	48
7.1.4.2	Registered State .....	48
7.1.4.3	Notifying .....	48
7.1.4.4	Suspending Notification .....	49
7.1.4.5	Normal Load state .....	49
7.1.4.6	Application overload state .....	49
7.1.4.7	Internal overload .....	49
7.1.4.8	Internal and application overload .....	50
7.1.5	IPFaultManager .....	50
7.1.5.1	Framework Active state .....	50
7.1.5.2	Framework Faulty state .....	50
7.1.5.3	The Service Activity Test state .....	50
7.1.5.4	The Framework Activity Test state .....	50
7.1.6	IpHeartbeatmgmt .....	51
7.1.6.1	Application not supervised .....	51
7.1.6.2	Application supervised .....	51
7.1.7	IpHeartBeat .....	52
7.1.7.1	FW Supervised by Application state .....	52
7.1.8	IpOAM .....	52
7.1.8.1	Active state .....	53
7.1.9	IpServiceRegistration .....	53
7.1.9.1	Registering SCF .....	53
7.1.9.2	SCF Registered .....	53
7.2	Generic Call Control .....	54
7.2.1	Call Control Manager .....	54
7.2.1.1	Active state .....	54
7.2.1.2	Notification terminated state .....	54
7.2.2	Call .....	55
7.2.2.1	Active state .....	55

7.2.2.1.1	1 Party in Call state .....	55
7.2.2.1.2	2 Parties in Call state .....	56
7.2.2.3	Network released state.....	56
7.2.2.4	Finished state.....	56
7.2.2.5	Application released state.....	56
7.3	User Interaction.....	57
7.3.1	UI Manager .....	57
7.3.1.1	Active state .....	57
7.3.1.2	Notification Terminated state .....	57
7.3.2	UI .....	58
7.3.2.1	Active state .....	58
7.3.2.2	Release Pending state .....	58
7.3.3	UI Call .....	59
7.3.3.1	Active state .....	59
7.3.3.2	Release Pending state .....	59
7.4	Data Session.....	60
7.4.1	Active state .....	60
7.4.1.1	Setup state .....	60
7.4.1.2	Established state .....	60
7.4.2	Network Released state .....	61
7.4.3	Finished state.....	61
7.4.4	Application released state.....	61
7.5	Network User Location .....	62
7.5.1	Active state .....	62
7.6	User Status .....	62
7.6.1	Active State .....	63
8	Data Definitions .....	63
8.1	Common Data definitions .....	63
8.1.1	Primitive Data Types.....	63
8.1.2	Structured data types classification .....	63
8.1.2.1	Structures made of data elements .....	63
8.1.2.2	Tagged choice of data elements (i.e.: Free unions) .....	63
8.1.2.3	Collection of data elements .....	64
8.1.2.4	References .....	64
8.1.3	Interface Definitions.....	64
8.1.3.1	IpOsa .....	64
8.1.3.2	IpOsaRef.....	64
8.1.3.3	IpOsaRefRef .....	64
8.1.3.4	IpService.....	64
8.1.3.5	IpServiceRef.....	65
8.1.3.6	IpServiceRefRef .....	65
8.1.4	Non primitive and structured type types definition .....	65
8.1.4.1	TpAssignmentID .....	65
8.1.4.2	TpSessionID .....	65
8.1.4.3	TpSessionIDSet .....	65
8.1.4.4	TpDuration .....	65
8.1.4.5	TpResult .....	65
8.1.4.6	TpResultType .....	65
8.1.4.7	TpResultFacility .....	66
8.1.4.8	TpResultInfo.....	66
8.1.4.9	TpDate .....	67
8.1.4.10	TpTime .....	68
8.1.4.11	TpDateAndTime .....	68
8.1.4.12	TpAddress.....	69
8.1.4.13	TpAddressSet.....	69
8.1.4.14	TpAddressPlan.....	69
8.1.4.15	TpAddressPresentation .....	69
8.1.4.16	TpAddressRange.....	70
8.1.4.17	TpAddressScreening .....	70
8.1.4.18	TpAddressError .....	70
8.1.4.19	TpURL.....	71

8.1.4.20	TpPrice.....	71
8.1.4.21	TpAoCInfo.....	71
8.1.4.22	TpAoCOrder .....	71
8.1.4.23	TpCallAoCOrderCategory.....	71
8.1.4.24	TpChargeAdviceInfo .....	71
8.1.4.25	TpCAIElements .....	72
8.1.4.26	TpChargePerTime.....	72
8.2	Framework Data Definitions.....	72
8.2.1	Common Framework Data Definitions .....	72
8.2.1.1	TpClientAppID.....	72
8.2.1.2	TpClientAppIDList .....	73
8.2.1.3	TpEntOpID .....	73
8.2.1.4	TpEntOpIDList.....	73
8.2.1.5	TpService .....	73
8.2.1.6	TpServiceList .....	73
8.2.1.7	TpServiceDescription .....	73
8.2.1.8	TpServiceID .....	73
8.2.1.9	TpServiceIDList .....	73
8.2.1.10	TpServiceIDRef .....	73
8.2.1.11	TpServiceNameString .....	74
8.2.1.12	TpServiceSpecString .....	74
8.2.1.13	TpUniqueServiceNumber .....	74
8.2.1.14	TpPropertyStruct .....	74
8.2.1.15	TpPropertyStructList .....	74
8.2.1.16	TpServicePropertyName .....	75
8.2.1.17	TpServicePropertyNameList .....	75
8.2.1.18	TpServicePropertyValue .....	75
8.2.1.19	TpServicePropertyValueList .....	75
8.2.1.20	TpServiceProperty .....	75
8.2.1.21	TpServicePropertyList .....	75
8.2.1.22	TpServiceTypeDescription .....	76
8.2.1.23	TpServiceTypeName .....	76
8.2.1.24	TpServiceTypeNameList .....	76
8.2.2	Trust and Security Management Data Definitions .....	76
8.2.2.1	TpAccessType .....	76
8.2.2.2	TpAuthType .....	76
8.2.2.3	TpAuthCapability .....	77
8.2.2.4	TpAuthCapabilityList .....	77
8.2.2.5	TpInterfaceName .....	77
8.2.2.6	TpServiceAccessControl .....	77
8.2.2.7	TpServiceToken .....	77
8.2.2.8	TpSignatureAndServiceMgr .....	78
8.2.2.9	TpSigningAlgorithm .....	78
8.2.3	Integrity Management Data Definitions .....	78
8.2.3.1	TpActivityTestRes .....	78
8.2.3.2	TpFaultStatsRecord .....	78
8.2.3.3	TpFaultStatsSet .....	78
8.2.3.4	TpActivityTestId .....	79
8.2.3.5	TpInterfaceFault .....	79
8.2.3.6	TpSvcUnavailReason .....	79
8.2.3.7	TpAPIUnavailReason .....	79
8.2.3.8	TpLoadLevel .....	80
8.2.3.9	TpLoadThreshold .....	80
8.2.3.10	TpLoadInitVal .....	80
8.2.3.11	TpTimeInterval .....	80
8.2.3.12	TpLoadPolicy .....	80
8.2.3.13	TpLoadStatistic .....	80
8.2.3.14	TpLoadStatList .....	81
8.2.3.15	TpLoadStatusError .....	81
8.2.3.16	TpLoadStatisticError .....	81

8.2.3.17	TpLoadStatisticErrorList .....	81
8.3	Generic Call Control Data Definitions .....	81
8.3.1	Interface definitions .....	81
8.3.1.1	IpAppCall .....	81
8.3.1.2	IpAppCallRef .....	81
8.3.1.3	IpAppCallRefRef .....	81
8.3.1.4	IpAppCallControlManager .....	81
8.3.1.5	IpAppCallControlManagerRef .....	81
8.3.1.6	IpCall .....	81
8.3.1.7	IpCallRef .....	82
8.3.1.8	IpCallRefRef .....	82
8.3.1.9	IpCallControlManager .....	82
8.3.1.10	IpCallControlManagerRef .....	82
8.3.2	Event Notification data definitions .....	82
8.3.2.1	TpCallEventName .....	82
8.3.2.2	TpCallEventCriteria .....	82
8.3.2.3	TpCallEventCriteriaResult .....	83
8.3.2.4	TpCallEventCriteriaResultSet .....	83
8.3.2.5	TpCallNotificationType .....	83
8.3.2.6	TpCallEventInfo .....	83
8.3.3	Generic Call Control Type definitions .....	84
8.3.3.1	TpCallAlertingMechanism .....	84
8.3.3.2	TpCallAppInfo .....	84
8.3.3.3	TpCallAppInfoType .....	84
8.3.3.4	TpCallAppInfoSet .....	85
8.3.3.5	TpCallBearerService .....	85
8.3.3.6	TpCallChargePlan .....	85
8.3.3.7	TpCallChargeOrder .....	86
8.3.3.8	TpCallChargeOrderCategory .....	86
8.3.3.9	TpCallEndedReport .....	86
8.3.3.10	TpCallError .....	87
8.3.3.11	TpCallAdditionalErrorInfo .....	87
8.3.3.12	TpCallErrorType .....	87
8.3.3.13	TpCallFault .....	88
8.3.3.14	TpCallIdentifier .....	88
8.3.3.15	TpCallIdentifierRef .....	88
8.3.3.16	TpCallInfoReport .....	88
8.3.3.17	TpCallInfoType .....	89
8.3.3.18	TpCallMonitorMode .....	89
8.3.3.19	TpCallNetworkAccessType .....	89
8.3.3.20	TpCallOverloadType .....	89
8.3.3.21	TpCallServiceCode .....	90
8.3.3.22	TpCallServiceCodeType .....	90
8.3.3.23	TpCallPartyCategory .....	90
8.3.3.24	TpCallReleaseCause .....	91
8.3.3.25	TpCallReport .....	91
8.3.3.26	TpCallAdditionalReportInfo .....	91
8.3.3.27	TpCallReportRequest .....	92
8.3.3.28	TpCallAdditionalReportCriteria .....	92
8.3.3.29	TpCallReportRequestSet .....	92
8.3.3.30	TpCallReportType .....	92
8.3.3.31	TpCallServiceCode .....	94
8.3.3.32	TpCallTeleService .....	94
8.3.3.33	TpCallSuperviseReport .....	95
8.3.3.34	TpCallSuperviseTreatment .....	96
8.4	User Interaction Data Definitions .....	96
8.4.1	Interface definitions .....	96
8.4.1.1	IpUI .....	96
8.4.1.2	IpUIRef .....	96
8.4.1.3	IpUIRefRef .....	96
8.4.1.4	IpUIManager .....	96
8.4.1.5	IpUIManagerRef .....	96

8.4.1.6	IpAppUI .....	96
8.4.1.7	IpAppUIRef.....	96
8.4.1.8	IpAppUIRefRef.....	96
8.4.1.9	IpAppUIManager .....	97
8.4.1.10	IpAppUIManagerRef .....	97
8.4.2	Type definitions.....	97
8.4.2.1	TpUICallIdentifier.....	97
8.4.2.2	TpUICallIdentifierRef .....	97
8.4.2.3	TpUICollectCriteria.....	97
8.4.2.4	TpUIError.....	98
8.4.2.5	TpUIEventCriteria.....	98
8.4.2.6	TpUIEventInfo .....	99
8.4.2.7	TpUIEventInfoDataType.....	99
8.4.2.8	TpUIFault .....	99
8.4.2.9	TpUIIdentifier .....	99
8.4.2.10	TpUIIdentifierRef .....	99
8.4.2.11	TpUIInfo .....	100
8.4.2.12	TpUIInfoType .....	100
8.4.2.13	TpUIMessageCriteria.....	100
8.4.2.14	TpUIReport .....	100
8.4.2.15	TpUIResponseRequest.....	102
8.4.2.16	TpUIVariableInfo .....	102
8.4.2.17	TpUIVariableInfoSet .....	102
8.4.2.18	TpUIVariablePartType .....	102
8.5	Data Session Control Data Definitions .....	102
8.5.1	Interface definitions.....	103
85.1.1	IpAppDataSession .....	103
85.1.2	IpAppDataSessionRef .....	103
85.1.3	IpAppDataSessionRefRef .....	103
85.1.4	IpAppDataSessionControlManager .....	103
85.1.5	IpAppDataSessionControlManagerRef .....	103
85.1.6	IpDataSession .....	103
85.1.7	IpDataSessionRef .....	103
85.1.8	IpDataSessionRefRef .....	103
85.1.9	IpDataSessionControlManager .....	103
85.1.10	IpDataSessionManagerRef .....	103
85.2	Event Notification data definitions .....	103
85.2.1	TpDataSessionEventName .....	103
85.2.2	TpDataSessionMonitorMode .....	104
85.2.3	TpDataSessionEventCriteria .....	104
85.2.4	TpDataSessionEventInfo .....	104
85.2.5	TpDataSessionChargePlan .....	104
85.2.6	TpDataSessionChargeOrder .....	105
85.2.7	TpDataSessionChargeOrderCategory .....	105
85.2.8	TpChargePerVolume .....	106
85.2.9	TpDataSessionIdentifier .....	106
85.2.10	TpDataSessionError .....	106
85.2.11	TpDataSessionAdditionalErrorInfo .....	106
85.2.12	TpDataSessionErrorType .....	106
85.2.13	TpDataSessionFault .....	107
85.2.14	TpDataSessionReleaseCause .....	107
85.2.15	TpDataSessionSuperviseVolume .....	107
85.2.16	TpDataSessionSuperviseReport .....	108
85.2.17	TpDataSessionSuperviseTreatment .....	108
85.2.18	TpDataSessionReport .....	108
85.2.19	TpDataSessionAdditionalReportInfo .....	108
85.2.20	TpDataSessionReportRequest .....	109
85.2.21	TpDataSessionReportRequestSet .....	109
85.2.22	TpDataSessionReportType .....	109
85.2.23	TpDataSessionEventCriteriaResultSetRef .....	109
85.2.24	TpDataSessionEventCriteriaResultSet .....	109
85.2.25	TpDataSessionEventCriteriaResult .....	109

8.6	Network User Location and User Status Data definitions.....	109
8.6.1	Interface Definitions .....	109
8.6.1.1	IpAppUserStatus .....	109
8.6.1.2	IpAppUserStatusRef.....	109
8.6.1.3	IpUserStatus .....	110
8.6.1.4	IpAppUserLocationCamel.....	110
8.6.1.5	IpAppUserLocationCamelRef.....	110
8.6.1.6	IpUserLocationCamel .....	110
8.6.2	Common Data Definitions for Network User Location and User Status.....	110
8.6.2.1	TpGeographicalPosition .....	110
8.6.2.2	TpLocationUncertaintyShape .....	113
8.6.2.3	TpMobilityDiagnostic .....	113
8.6.2.4	TpMobilityError .....	114
8.6.2.5	TpMobilityStopAssignmentData.....	114
8.6.2.6	TpMobilityStopScope .....	114
8.6.3	Network User Location Data Definitions .....	115
8.6.3.1	TpLocationCellIDOrLAI.....	115
8.6.3.2	TpLocationTriggerCamel .....	115
8.6.3.3	TpUserLocationCamel .....	115
8.6.3.4	TpUserLocationCamelSet .....	116
8.7	User Status Data Definitions .....	116
8.7.1.1	TpUserStatus .....	116
8.7.1.2	TpUserStatusSet .....	116
8.7.1.3	TpUserStatusIndicator .....	116
8.8	Terminal Capabilities Data Definitions.....	116
8.8.1	Interface Definitions.....	116
8.8.1.1	IpTerminalCapabilities .....	116
8.8.1.2	IpTerminalCapabilitiesRef .....	116
8.8.2	Terminal Capabilities Data Definitions .....	117
8.8.2.1	terminalIdentity .....	117
8.8.2.2	TpTerminalCapabilities .....	117
8.8.2.3	TpTerminalCapabilitiesError .....	117
9	IDL Interface Definitions .....	118
9.1	Generic IDL .....	118
9.2	Framework IDL .....	126
9.2.1	Common Data Types for the Framework .....	126
9.2.2	Service Discovery IDL .....	129
9.2.3	Trust and Security Management IDL .....	130
9.2.4	Integrity Management IDL .....	137
9.2.4	Registration IDL .....	149
9.3	Call Control .....	150
9.3.1	Common Data Types for Call Control .....	150
9.3.2	Generic Call Control IDL .....	156
9.3.3	Enhanced Call Control IDL .....	159
9.4	User Interaction IDL .....	162
9.4.1	Common data types for User Interaction .....	162
9.4.2	Generic User Interaction IDL .....	164
9.5	Data Session Control .....	168
9.6	Network User Location and User Status IDL .....	173
9.6.1	Common definitions for Network User Location and User Status: MM.idl .....	173
9.6.2	Network User Location: MMul.idl .....	176
9.6.3	User Status: MMus.idl .....	180
9.6.4	Terminal Capabilities: TERMCAP.idl .....	183
	<b>Annex A (informative): Change history .....</b>	<b>184</b>

---

## Foreword

This Technical Specification has been produced by the 3<sup>rd</sup> Generation Partnership Project (3GPP).

The contents of the present document are subject to continuing work within the TSG and may change following formal TSG approval. Should the TSG modify the contents of the present document, it will be re-released by the TSG with an identifying change of release date and an increase in version number as follows:

Version x.y.z

where:

- x the first digit:
  - 1 presented to TSG for information;
  - 2 presented to TSG for approval;
  - 3 or greater indicates TSG approved document under change control.
- y the second digit is incremented for all changes of substance, i.e. technical enhancements, corrections, updates, etc.
- z the third digit is incremented when editorial only changes have been incorporated in the document.

---

## 1 Scope

This document specifies the stage 3 of the Open Service Architecture (OSA) Application Programming Interface (API). The concepts and the functional architecture of the Open Service Architecture (API) are described by TS 23.127[2]. This document describes the stage 3 specification of the Open Service Architecture API.

The Open Service Architecture defines an architecture that enables service providers to make use of network functionality through an open standardised interface, i.e. the OSA API. The network functionality is described as Service Capability Servers. Within the OSA concepts the following Service Capability Servers are identified:

- CAMEL Service Environment (see in TS 23.078 [4])
- WAP execution platform (i.e. WAP Gateway & WAP Push Proxy, see in [13] )
- Home Location Register (HLR)

The stage 3 documentation of the OSA R'99 API consists of two parts:

- **The API specification (Part 1).**  
This is a normative stage 3 specification of the capabilities of the OSA R'99 API and describes the OSA API interface classes, containing class diagrams (see section 6), state transition diagrams (see section 7), SDLs (see section 8), data type definitions (section 9), and the IDLs (see section 10).
- **The Mapping specification of the OSA R'99 API and the network protocols (Part2).**  
This is an informative specification to provide an example how the OSA API can be mapped on the network protocols (i.e. MAP [7], CAP[8] and WAP[9]). It is an informative document, since this mapping is considered as implementation/vendor dependent. On the other hand this mapping will provide potential service designers with a better understanding of the relationship of the OSA API interface classes and the behavior of the network associated to these interface classes.

The OSA API Stage 3 activity is performed jointly with ETSI SPAN3's Service Provider Access Requirements activity. The contents of this document is related to the jointly owned 3GPP & ETSI document referred as the API Master document, which contains the API interface descriptions that are common and differentiated between ETSI & 3GPP.

---

## 2 References

References may be made to:

- a) Specific versions of publications (identified by date of publication, edition number, version number, etc.), in which case, subsequent revisions to the referenced document do not apply; or
- b) All versions up to and including the identified version (identified by "up to and including" before the version identity); or
- c) All versions subsequent to and including the identified version (identified by "onwards" following the version identity); or
- d) Publications without mention of a specific version, in which case the latest version applies.

A non-specific reference to an ETSI shall also be taken to refer to later versions published as an EN with the same number.

- [1] 3G TR 21.905: "3G Vocabulary"
- [2] 3G TS 23.127: "Virtual Home Environment / Open Service Architecture"
- [3] 3G TS 23.057: "Mobile Station Application Execution Environment (MExE)"
- [4] 3G TS 23.078: "CAMEL Phase 3, stage 2"
- [5] 3G TS 22.101: "Universal Mobile Telecommunications System (UMTS): Service Aspects; Service Principles"
- [6] World Wide Web Consortium Composite Capability/Preference Profiles (CC/PP): A user side framework for content negotiation ([www.w3.org](http://www.w3.org))
- [7] 3G TS 29.002: "Mobile Application Part (MAP)"
- [8] 3G TS 29.078: "CAMEL Phase 3, , CAMEL Application Part (CAP) Specification"
- [9] Wireless Application Protocol (WAP), Version 1.2, UAProf Specification ([www.wapforum.org](http://www.wapforum.org))
- [10] Wireless Application Protocol (WAP), version 1.2, WAP Service Indication specification, ([www.wapforum.org](http://www.wapforum.org))
- [11] Wireless Application Protocol (WAP), version 1.2, WAP Push Architecture Overview ([www.wapforum.org](http://www.wapforum.org))
- [12] Wireless Application Protocol (WAP), version 1.2, WAP Architecture ([www.wapforum.org](http://www.wapforum.org))
- [13] SUN IDL Compiler ([www.javasoft.com/products/jdk/idl/index.html](http://www.javasoft.com/products/jdk/idl/index.html))
- [14] UML Unified Modelling Language ([www.rational.com/uml](http://www.rational.com/uml))
- [15] Object Management Group ([www.omg.org](http://www.omg.org))
- [16] 3G TS 22.002: "Circuit Bearer Services supported by a PLMN"
- [17] 3G TS 22.003: "Circuit Teleservices supported by a PLMN"
- [18] 3G TS 24.002: "Public Land Mobile Network (PLMN) Access Reference Configuration"
- [19] ITU-T Q.763: "Signalling System No. 7 – ISDN user part formats and codes"
- [20] ITU-T Q.931: "ISDN user-network interface layer 3 specification for basic call control"
- [21] ISO 8601: "Data elements and interchange formats -- Information interchange -- Representation of dates and times"
- [22] ISO 4217: "Codes for the representation of currencies and funds "

---

## 3 Definitions and abbreviations

### 3.1 Definitions

For the purposes of this specification, the following definitions apply:

**Applications:** Services, which are designed using service capability features.

**Gateway:** Synonym for Service Capability Server. From the viewpoint of applications, a Service Capability Server can be seen as a gateway to the core network.

**HE-VASP:** Home Environment Value Added Service Provider. This is a VASP that has an agreement with the Home Environment to provide services.

**Home Environment:** responsible for overall provision of services to users

**Local Service:** A service, which can be exclusively provided in the current serving network by a Value Added Service Provider.

**OSA Interface:** Standardised Interface used by application to access service capability features.

**Personal Service Environment:** contains personalised information defining how subscribed services are provided and presented towards the user. The Personal Service Environment is defined in terms of one or more User Profiles.

**Service Capabilities:** Bearers defined by parameters, and/or mechanisms needed to realise services. These are within networks and under network control.

**Service Capability Feature:** Functionality offered by service capabilities that are accessible via the standardised OSA interface

**Service Capability Server:** Functional Entity providing OSA interfaces towards an application

**User Interface Profile:** Contains information to present the personalised user interface within the capabilities of the terminal and serving network.

**User Profile:** This is a label identifying a combination of one user interface profile, and one user services profile.

**User Services Profile:** Contains identification of subscriber services, their status and reference to service preferences.

**Value Added Service Provider:** provides services other than basic telecommunications service for which additional charges may be incurred.

**Virtual Home Environment:** A concept for personal service environment portability across network boundaries and between terminals.

Further definitions are given in TS 22.101 [5].

## 3.2 Abbreviations

For the purposes of this TS the following abbreviations apply:

CAMEL	Customised Application For Mobile Network Enhanced Logic
CSE	Camel Service Environment
HE	Home Environment
HE-VASP	Home Environment Value Added Service Provider
HLR	Home Location Register
IDL	Interface Description Language
MAP	Mobile Application Part
ME	Mobile Equipment
MExE	Mobile Station (Application) Execution Environment
MS	Mobile Station
MSC	Mobile Switching Centre
OSA	Open Service Architecture
PLMN	Public Land Mobile Network
PSE	Personal Service Environment
SAT	SIM Application Tool-Kit
SCP	Service Control Point
SIM	Subscriber Identity Module
SMS	Short Message Service
SMTP	Simple Mail Transfer Protocol
USIM	User Service Identity Module
VASP	Value Added Service Provider
VHE	Virtual Home Environment
WAP	Wireless Application Protocol
WGP	Wireless Gateway Proxy
WPP	Wireless Push Proxy

Further abbreviations are given in the TR 21.905 [1].

## 4 Open Service Architecture

The concepts and Architecture of the Open Service Architecture are described within [2]. Within this stage 2 document several Service Capability Features are identified. However for OSA API Release 99, the set of addressed Service Capability Features are limited to the following:

- Framework SCF
  - Service Discovery interface
  - Trust and Security Management interfaces (Initial Contact interfaces and Authentication interfaces)
  - Integrity Management interfaces (Load Manager interfaces, Fault Manager interfaces, OAM interfaces, Heart Beat interfaces)
  - Registration interfaces
- Call Control SCF
- User Interaction SCFs
  - Generic User Interaction SCF
  - Call User Interaction SCF
- Network User Location SCF
- User Status SCF
  - Terminal Capabilities SCF
  - Data Session SCF

The Framework API contains interfaces between the Application Server and the Framework, and between Network Service Capability Server (SCS) and the Framework.

The User Profiles are limited to the Terminal Capabilities for OSA R'99. Therefore, only limited functionality is available for the security within OSA R'99. The Framework & Network SCSs provide the following security mechanisms for OSA R'99:

- Checking the subscriber's registration to the SCS feature
- Checking the subscriber's activation of the SCS feature
- Checking the subscriber's privacy settings of the SCS feature

The purpose of the OSA API is to shield the complexity of the network, its protocols and specific implementation from the applications. This means that applications do not have to be aware of the network nodes a Service Capability Server interacts with in order to provide the Service Capability Features to the application. The specific underlying network and its protocols are transparent to the application.

For example, an application that has subscribed to the Network User Location SCF does not have to know whether the SCS provides location reports to the application based on information from the CSE or HLR. Similarly, the application does not have to know whether a message offered to the SCS for delivery to a terminal is actually sent by the SCS to the terminal via a WGP/WPP or SMS-C. It is the Service Capability Server that is capable of deciding how the message is to be sent. The OSA concept therefore leads to a shift of logic on dealing with the network from the applications to the Service Capability Servers.

## 5 Methodology

Following is a description of the methodology used for the establishment of stage 3 specification in the scope of 3GPP CN OSA.

### 5.1 Tools and Languages

The Unified Modelling Language (UML) [14] is used as the means to specify class and state transition diagrams. Additionally, Object Management Group's (OMG) [15] Interface Definition Language (IDL) is used as the means to programmatically define the interfaces. IDL files are either generated manually from class diagrams or by using a UML tool. In the case IDLs are manually written and/or being corrected manually, correctness has been verified using a CORBA2 (orbos/97-02-25) compliant IDL compiler, e.g. [13].

### 5.2 Packaging

A hierarchical packaging scheme is used to avoid polluting the global name space. The root is defined as:

`org.threegpp.osa`

Note that the CORBA module hierarchy defined in the IDLs does not necessarily parallels the logical UML package hierarchy.

### 5.3 Colours

For clarity, class diagrams follows a certain colour scheme. Blue for application interface packages and yellow for all the others.

### 5.4 Naming scheme

The following naming scheme is used for both documentation and IDLs.

#### **packages**

lowercase.

Using the domain-based naming (For example, `org.threegpp.osa`)

#### **classes, structures and types. Start with T**

`TpCapitalizedWithInternalWordsAlsoCapitalized`

#### **Exception class:**

`TpClassNameEndsWithException`

#### **Interface. Start with Ip:**

`IpThisIsAnInterface`

#### **constants:**

`P_UPPER_CASE_WITH_UNDERSCORES_AND_START_WITH_P`

#### **methods:**

`firstWordLowerCaseButInternalWordsCapitalized()`

#### **method's parameters**

`firstWordLowerCaseButInternalWordsCapitalized`

**collections (set, array or list types)**

TpCollectionEndsWithSet

**class/structure members**

FirstWordAndInternalWordsCapitalized

Spaces in between words are not allowed.

## 5.5 Error results

As OMG IDL supports exception handling with high efficiency, OSA methods communicate errors in the form of CORBA exceptions of type TpGeneralException in the IDLs; the CORBA methods themselves always return void. But in the documentation, errors are communicated using a return parameter of type TpGeneralResult.

## 5.6 References

In the interface specification whenever parameters are to be passed by reference, the “Ref” suffix is appended to their corresponding data type (e.g. IpAnInterfaceRef anInterface), a reference can also be viewed as a logical indirection. Therefore, structured or primitive data type passed as *out* parameters are references. An interface passed as an *in* parameter is also a reference but an interface passed as an *out* parameter is a double indirection (i.e.: RefRef)

Original Data type	IN parameter declaration	OUT parameter declaration
TpPrimitive	parm : IN TpPrimitive	parm : OUT TpPrimitiveRef
TpStructured	parm : IN TpStructured	parm : OUT TpStructuredRef
IpInterface	parm : IN IpInterfaceRef	parm : OUT IpInterfaceRefRef

In IDL, however, the following rules apply:

- Interfaces are implicitly passed by reference.
- *out* parameters are also implicitly passed by reference.

This leads to:

- Interface as an *in* parameter: Passed by Reference.
- Structure or primitive type as an *in* parameter: Passed by Value.
- Structure or primitive type as an *out* parameter: Passed by Reference.
- Interface as an *out* parameter: As reference passed by reference.

To simplify the documentation without adding ambiguities, parameters (interfaces, structures and primitive data types) are used as is when specified as *in* or *out* parameters in the IDL. This means that there will be no “Ref” added after the data types of parameters in the IDL.

## 5.7 Number of out parameters

In order to support mapping to as many languages as possible, there is only 1 out parameter allowed per operation.

## 5.8 Strings and Collections

For character strings, the *String* data type is used without regard to the maximum length of the string. In IDL, the data type *String* is typedefed<sup>1</sup> from the CORBA primitive *string*. This CORBA primitive is made up of a length and a variable array of byte.

For homogeneous collections of instances of a particular data type the following naming scheme is used: <datatype>Set. In OMG IDL, this maps to a sequence of the data type. A CORBA sequence is implicitly made of a length and a variable array of elements of the same type.

**Example:** `typedef sequence<TpSessionID> TpSessionIDSet;`

Collection types can be implemented (for example, in C++) as a structure containing an integer for the *number* part, and an array for the *data* part.

**Example:** The *TpAddressSet* data type may be defined in C++ as:

```
typedef struct {
    short      number;
    TpAddress  address [ ];
} TpAddressSet;
```

The array "address" is allocated dynamically with the exact number of required *TpAddress* elements based on "number".

## 5.9 Prefixes

OSA constants and data types are not defined in the global name space but in the *org.threegpp.osa* module.

## 5.10 Naming space across CORBA modules

The following shows the naming space used in this specification.

```
module org {

    module threegpp { // cannot use 3gpp, names need to start with letter

        module osa {

            // The fully qualified name of the following constant
            // is org::threegpp::osa::P_THIS_IS_AN_OSA_GLOBAL_CONST
            const long P_THIS_IS_AN_OSA_GLOBAL_CONST= 1999;

            // Add other OSA global constants and types here

        module framework {
            // no scoping required to access P_THIS_IS_AN_OSA_GLOBAL_CONST
        }
    }
}
```

---

<sup>1</sup> A *typedef* is a type definition declaration in IDL.

```
    const long P_FW_CONST= THIS_IS_AN_OSA_GLOBAL_CONST;  
};  
  
module mm {  
    // scoping required to access P_FW_CONST  
    const long P_M_CONST= framework::P_FW_CONST;  
};  
  
};  
};
```


## 6 Class diagrams

Class diagrams are specified in UML: interface classes are shown as interface names within shaded rectangular boxes; relationships and generalizations as lines connecting pairs of interface classes.

All OSA interface classes should be packaged into the org.threegpp.osa module. Further sub-packaging is an implementation decision, but this section proposes a way to do it. Using this recommended packaging, a top-down approach is followed in the subsequent sections. Note that UML packaging is only a logical packaging and does not necessarily reflects IDL packaging.

### 6.1 Class diagrams common across OSA

All application and framework interfaces inherit from IpOsa interface. Network Service Capability Features on the other hand inherit from the common IpService interface. The corresponding interfaces that must be implemented by the application (e.g. for API callbacks) are denoted as 'Application Interface'.



**Figure 6-1: OSA base interfaces**

#### 6.1.1 Base OSA interface

All application and framework interfaces inherit from the following interface.

<<Interface>>
IpOsa

#### 6.1.2 Generic Service Capability Feature interface

All Network SCF's interfaces inherit from the following interface.

<<Interface>>
IpService


setCallback(appInterface : in IpOsaRef) : TpResult

## 6.2 Class diagrams for the Framework

This section specifies the class diagrams that define the Framework, and proposes a way to package them.


### 6.2.1 Top level Framework packages

The top level view of the Framework consists of the following four packages:




**Figure 6-2: Framework top level packages**

The first two packages are de-composed in the following way:



Consists of

- *PappTrustAndSecurityMgmt*
- *PAppIntegrityMgmt*




Consists of

- *PServiceDiscovery*
- *PTrustAndSecurityMgmt*
- *PIntegrityMgmt*


The latter two packages contain only one interface each:

- PFWFramework consists of the *Service Registration* Interface
- PSvcFramework consists of the *Service Factory* Interface

The top-level packages are de-composed as described above; between some of the resulting sub-packages there are dependencies, that reflect dependencies between any two classes in the sub-package. The following figure shows all this.


**Figure 6-3: Framework sub-packages**

### 6.2.2 Service Discovery

**Figure 6-4: Service Discovery Class Diagrams**


<code>&lt;&lt;Interface&gt;&gt;</code> <code>IpServiceDiscovery</code>
<code>listServiceTypes(listTypes: out TpServiceTypeNameListRef) : TpResult</code> <code>describeServiceType(name: in TpServiceTypeName, serviceTypeDescription: out TpServiceTypeDescriptionRef) : TpResult</code> <code>discoverService(serviceTypeName: in TpServiceTypeName, desiredPropertyList: in TpServicePropertyList, max: in TplInt32, serviceList: out TpServiceListRef) : TpResult</code> <code>listSubscribedServices(serviceList: out TpServiceListRef) : TpResult</code>

### 6.2.3 Trust and Security Management




**Figure 6-5: Trust and Security Management – Application and Framework Class Diagrams**


### 6.2.3.1 IpInitial



### 6.2.3.2 IpAppAuthentication



### 6.2.3.3 IpAuthentication



### 6.2.3.4 IpAccess

<p>&lt;&lt;Interface&gt;&gt;</p> <p>IpAccess</p>
<pre> obtainInterface( interfaceName: in TpInterfaceName, fwInterface: out IpOsaRefRef): TpResult obtainInterfaceWithCallback( interfaceName: in TpInterfaceName, applInterface: in IpOsaRef,     fwInterface: out IpOsaRefRef): TpResult  accessCheck( securityContext:: inTpString, securityDomain: inTpString, group : inTpString,     serviceAccessTypes: inTpString, serviceAccessControl: outTpServiceAccessControlRef): TpResult  selectService( serviceID: inTpServiceID, serviceProperties: inTpServicePropertyList,     serviceToken: outTpServiceTokenRef): TpResult  signServiceAgreement( serviceToken: inTpServiceToken, agreementText: inTpString,     signingAlgorithm: inTpSigningAlgorithm, signatureAndServiceMgr: outTpSignatureAndServiceMgrRef ): TpResult  terminateServiceAgreement( serviceToken: inTpServiceToken, terminationText: inTpString,     digitalSignature: inTpString): TpResult  endAccess(endAccessProperties: inTpPropertyList) : TpResult </pre>

### 6.2.3.5 IpAppAccess

<p>&lt;&lt;Interface&gt;&gt;</p> <p>IpAppAccess</p>
<pre> signServiceAgreement( serviceToken: inTpServiceToken, agreementText: inTpString,     signingAlgorithm: inTpSigningAlgorithm, digitalSignature: outTpStringRef): TpResult  terminateServiceAgreement( serviceToken: inTpServiceToken, terminationText: inTpString,     digitalSignature: inTpString): TpResult  terminateAccess( terminationText: inTpString, signingAlgorithm: inTpSigningAlgorithm,     digitalSignature: inTpStringRef) : TpResult </pre>

## 6.2.4 Integrity Management




Figure 6-6: Integrity Management – Application and Framework Class Diagrams


### 6.2.4.1 IpHeartBeatMgmt

<p style="text-align: center;"><b>&lt;&lt;Interface&gt;&gt;</b></p> <p style="text-align: center;"><b>IpHeartBeatMgmt</b></p>
<pre> enableHeartBeat(duration: in TpDuration, applInterface: in IpAppHeartBeatRef, session: out TpSessionIDRef) : TpResult  disableHeartBeat(session: in TpSessionID) : TpResult  changeTimePeriod(duration: in TpDuration, session: in TpSessionID) : TpResult   </pre>


### 6.2.4.2 IpAppHeartBeatMgmt

<p style="text-align: center;"><b>&lt;&lt;Interface&gt;&gt;</b></p> <p style="text-align: center;"><b>IpAppHeartBeatMgmt</b></p>
<pre> enableAppHeartBeat(duration: in TpDuration, fwlInterface: in IpHeartBeatRef, session: in TpSessionID) : TpResult  disableAppHeartBeat(session: in TpSessionID) : TpResult  changeTimePeriod(duration: TpDuration, session: in TpSessionID) : TpResult   </pre>


#### 6.2.4.3 IpHeartBeat



#### 6.2.4.4 IpAppHeartBeat



#### 6.2.4.5 IpLoadManager



#### 6.2.4.6 IpAppLoadManager

<p>&lt;&lt;Interface&gt;&gt;</p> <p>IpAppLoadManager</p>
<p>queryAppLoadReq(servicIDs: in TpServiceIDList, timeInterval :TpTimeInterval) :TpResult      queryLoadRes(loadStatistics : in TpLoadStatList) :TpResult      queryLoadErr(loadStatisticsError : in TpLoadStatErrList) :TpResult      disableLoadControl(servicIDs: in TpServiceIDList) :TpResult      enableLoadControl(loadStatistics : in TpLoadStatList ) :TpResult      resumeNotification() :TpResult      suspendNotification() :TpResult</p>


#### 6.2.4.7 IpFaultManager

<p>&lt;&lt;Interface&gt;&gt;</p> <p>IpFaultManager</p>
<p>activityTestReq(activityTestID: in TpActivityTestID, svcID: in TpServiceID, appID: in TpClientAppID): TpResult      appActivityTestRes(activityTestID: in TpActivityTestID, activityTestResult: in TpActivityTestRes): TpResult      svcUnavailableInd(serviceID: in TpServiceID, appID: in TpClientAppID): TpResult      genFaultStatsRecordReq(timePeriod: in TpTimeInterval, serviceIDList: in TpServiceIDList, appID: in TpClientAppID): TpResult</p>


#### 6.2.4.8 IpAppFaultManager

<p>&lt;&lt;Interface&gt;&gt;</p> <p>IpAppFaultManager</p>
<p>activityTestRes(activityTestID: in TpActivityTestID, activityTestResult: in TpActivityTestRes): TpResult      appActivityTestReq(activityTestID: in TpActivityTestID): TpResult      fwFaultReportInd(fault: in TpInterfaceFault): TpResult      fwFaultRecoveryInd(fault: in TpInterfaceFault): TpResult      svcUnavailableInd(serviceID: in TpServiceID, reason: in TpSvcUnavailReason): TpResult      genFaultStatsRecordRes(faultStatistics: in TpFaultStatsRecord, serviceIDs: in TpServiceIDList): TpResult</p>


#### 6.2.4.9 IpOAM




#### 6.2.4.10 IpAppOAM



### 6.2.5 Service Registration




**Figure 6-7: Service Registration Class Diagram**



## 6.2.6 Service Factory




**Figure 6-8: Service Factory Class Diagram**



## 6.3 Generic Call Control

The Generic Call Control SCF provides the basic call control capabilities for the API. It allows calls to be instantiated from the network and routed through the network. The call model is based around a central call model that has zero to two call legs that are active (i.e., being routed or connected), each of which represents the logical relationship between the call and an address. However, the application does not have direct access to the call legs. Generic Call Control supports functionality to allow call routing and call management for Camel Phase 3 and earlier services.

Generic Call Control is represented by the IpCallManager and IpCall interfaces that interface to services provided by the network. Some methods are asynchronous, in that they do not lock a thread into waiting whilst a transaction performs. In this way, the client machine can handle many more calls, than one that uses synchronous message calls. To handle responses and reports, the developer must implement IpAppCallManager and IpAppCall.



**Figure 6-9: Generic Call Control Packages**




Figure 6-10: Generic Call Control Class diagram Interface Classes

This section contains the detailed interface specifications of the interfaces shown in the Generic Call Control Class diagram.

### 6.3.1 Interface Classes

#### 6.3.1.1 IpAppCallControlManager

<<Interface>> <b>IpAppCallControlManager</b>
callAborted(callReference : in TpSessionID) : TpResult callEventNotify(callReference : in TpCallIdentifier , eventInfo : in TpCallEventInfo , assignmentID : in TpAssignmentID , applInterface : out IpAppCallRefRef) : TpResult callNotificationInterrupted() : TpResult callNotificationContinued(): TpResult

#### 6.3.1.2 IpCallControlManager

<<Interface>> <b>IpCallControlManager</b>
enableCallNotification(applInterface : in IpAppCallControlManagerRef , eventCriteria : in TpCallEventCriteria , assignmentID : out TpAssignmentIDRef) : TpResult disableCallNotification(assignmentID : in TpAssignmentID) : TpResult changeCallNotification(assignmentID : in TpAssignmentID , eventCriteria : in TpCallEventCriteria) : TpResult getCriteria(eventCriteria : out TpCallEventCriteriaResultSet) : TpResult

#### 6.3.1.3 IpAppCall

<<Interface>> <b>IpAppCall</b>
routeRes(callSessionID : in TpSessionID , eventReport : in TpCallReport, callLegSessionID : in TpSessionID) : TpResult routeErr(callSessionID : in TpSessionID , errorIndication : in TpCallError, callLegSessionID : in TpSessionID) : TpResult getCallInfoRes(callSessionID : in TpSessionID , callInfoReport : in TpCallInfoReport) : TpResult getCallInfoErr(callSessionID : in TpSessionID , errorIndication : in TpCallError) : TpResult superviseCallRes(callSessionID : in TpSessionID , report : in TpCallSuperviseReport , usedTime : in TpDuration) : TpResult superviseCallErr(callSessionID : in TpSessionID , errorIndication : in TpCallError) : TpResult callFaultDetected(callSessionID : in TpSessionID , fault : in TpCallFault) : TpResult callEnded(callSessionID : in TpSessionID , report : in TpCallEndedReport ) : TpResult

### 6.3.1.4 IpCall

<<Interface>> <b>IpCall</b>
<pre>routeReq(callSessionID : in TpSessionID , responseRequested : in TpCallReportRequestSet ,           targetAddress : in TpAddress , originatingAddress : in TpAddress , originalDestinationAddress : in           TpAddress , redirectingAddress : in TpAddress , applInfo : in TpCallAppInfoSet , callLegSessionID : out           TpSessionIDRef ) : TpResult  release(callSessionID : in TpSessionID , cause : in TpCallReleaseCause) : TpResult  deassignCall(callSessionID : in TpSessionID) : TpResult  getCallInfoReq(callSessionID : in TpSessionID , callInfoRequested : in TpCallInfoType) : TpResult  setCallChargePlan(callSessionID : in TpSessionID , callChargePlan : in TpCallChargePlan) : TpResult  superviseCallReq(callSessionID : in TpSessionID , time : in TpDuration , treatment : in           TpCallSuperviseTreatment) : TpResult  setAdviceOfCharge(callSessionID : in TpSessionID , aOCInfo : in TpAoCInfo , tariffSwitch : in TpDuration)           : TpResult</pre>


## 6.4 Generic User Interaction and Call User Interaction

The Generic User Interaction interface and Call User Interaction SCFs are used by applications to interact with end users.


The GUI is represented by the `IpUIManager`, `IpUI` and `IpUICall` interfaces that interface to service capabilities provided by the network.

The `IpUI` Interface provides functions to send information to, or gather information from the user, i.e. this interface allows applications to send SMS and USSD messages. An application can use this interface independently of other SCFs. The `IpUICall` Interface provides functions to send information to, or gather information from the user (or call party) attached to a call.

To handle responses and reports, the developer must implement `IpAppUIManager`, `IpAppUI` and `IpAppUICall` interfaces to provide the callback mechanism.



**Figure 6-11: Generic User Interaction Packages**



**Figure 6-12: Generic User interaction Class diagram**

#### 6.4.1 Relation between IpCall and IpUICall during call related user interaction

For call related user interaction, the **IpUICall** Interface provides functions to send information to, or gather information from the user (or call party) attached to a call. This means that there is a relationship between a specific Call object and a UICall object. This is shown in the figure below.



**Figure 6-13: Relation between the UICall and the Call object.**

In case a call requires user interaction, the application requests the UIManager to create the UICall object and provides a reference to the specific Call object. In this way the gateway is able to link the two objects together. It depends on the actual state of the call whether user interaction is really allowed.

## 6.4.2 Interface Classes

This section contains the detailed interface specifications of the interfaces shown in the Generic User Interaction Class diagram.

### 6.4.2.1 IpAppUIManager

<pre>&lt;&lt;Interface&gt;&gt; IpAppUIManager</pre>
<pre>userInteractionAborted(userInteraction : in TpUIIdentifier) : TpResult userInteractionEventNotify(ui : in TpUIIdentifier , eventInfo : in TpUIEventInfo ,                            assignmentID : in TpAssignmentID , applInterface : out IpAppUIRefRef ) : TpResult userInteractionNotificationInterrupted(): TpResult userInteractionNotificationContinued(): TpResult</pre>

### 6.4.2.2 IpUIManager

<pre>&lt;&lt;Interface&gt;&gt; IpUIManager</pre>
<pre>createUI(appUI : in IpAppUIRef , userAddress : in TpAddress , userInteraction : out TpUIIdentifierRef) : TpResult createUICall(appUI : in IpAppUICallRef , callIdentifier : in TpCallIdentifier ,             callLegIdentifier : in TpCallLegIdentifier , userInteraction : out TpUICallIdentifierRef) : TpResult enableUINotification(applInterface : in IpAppUIManagerRef ,                       eventCriteria : in TpUIEventCriteria , assignmentID : out TpAssignmentIDRef) : TpResult disableUINotification(assignmentID : in TpAssignmentID) : TpResult</pre>

#### 6.4.2.3 IpAppUI

<<Interface>>
IpAppUI
sendInfoRes(userInteractionSessionID : in TpSessionID , assignmentID : in TpAssignmentID, response : in TpUIReport) : TpResult
sendInfoErr(userInteractionSessionID : in TpSessionID , assignmentID : in TpAssignmentID, error : in TpUIError) : TpResult
sendInfoAndCollectRes(userInteractionSessionID : in TpSessionID , assignmentID : in TpAssignmentID, response : in TpUIReport , info : in TpString) : TpResult
sendInfoAndCollectErr(userInteractionSessionID : in TpSessionID , assignmentID : in TpAssignmentID, error : in TpUIError) : TpResult
userInteractionFaultDetected(userInteractionSessionID : in TpSessionID , fault : in TpUIFault) : TpResult

#### 6.4.2.4 IpUI

<p>&lt;&lt;Interface&gt;&gt;</p> <p style="text-align: center;">IpUI</p>
<p>sendInfoReq(userInteractionSessionID : in TpSessionID , info : in TpUIInfo , variableInfo : in TpUIVariableInfoSet , repeatIndicator : in TpInt32 , responseRequested : in TpUIResponseRequest , assignmentID : out TpAssignmentIDRef) : TpResult</p> <p>sendInfoAndCollectReq(userInteractionSessionID : in TpSessionID , info : in TpUIInfo , variableInfo : in TpUIVariableInfoSet , criteria : in TpUICollectCriteria , responseRequested: in TpUIResponseRequest , assignmentID : out TpAssignmentIDRef) : TpResult</p> <p>release(userInteractionSessionID : in TpSessionID) : TpResult</p>

#### 6.4.2.5 IpAppUICall

<p>&lt;&lt;Interface&gt;&gt;</p> <p style="text-align: center;">IpAppUICall</p>
<p>abortActionRes(userInteractionSessionID : in TpSessionID , assignmentID : in TpAssignmentID) : TpResult</p> <p>abortActionErr(userInteractionSessionID : in TpSessionID , assignmentID : in TpAssignmentID , error : in TpUIError) : TpResult</p>


#### 6.4.2.6 IpUICall

<p>&lt;&lt;Interface&gt;&gt;</p> <p style="text-align: center;">IpUICall</p>
<p>abortActionReq(userInteractionSessionID : in TpSessionID, assignmentID : in TpAssignmentID) : TpResult</p>


## 6.5 Data Session Control

The Data Session Control provides a means to control *per data session basis* the establishment of a new data session. This means especially in the GPRS context that the establishment of a PDP session is modelled not the attach/detach mode. Change of terminal location is assumed to be managed by the underlying network and is therefore not part of the model. The underlying assumption is that a terminal initiates a data session and the application can reject the request for data session establishment, can continue the establishment or can continue and change the destination as requested by the terminal.

The modelling is similar to the Generic Call Control but assuming a simpler underlying state model. An IpDataSessionManager and IpDataSession object are the interfaces used by the application, whereas the IpAppDataSessionManager and the IpAppDataSession interfaces are implemented by the application.



**Figure 6-14: Data Session Control Packages**



**Figure 6-15: Data Session Control Class diagram Interface Classes**

This section contains the detailed interface specifications of the interfaces shown in the Data Session Control Class diagram.

## 6.5.1 Interface Classes

### 6.5.1.1 IpAppDataSessionControlManager

<<Interface>> IpAppDataControlManager
<pre> dataSessionAborted(dataSessionID : in TpSessionID) : TpResult dataSessionEventNotify(dataSessionReference : in TpdataSessionIdentifier , eventInfo : in TpDataSessionEventInfo , assignmentID : in TpAssignmentID , applInterface : out IpAppdataSessionRefRef) : TpResult dataSessionNotificationContinued() : TpResult dataSessionNotificationInterrupted(): TpResult </pre>

### 6.5.1.2 IpDataSessionControlManager

<p style="text-align: center;">&lt;&lt;Interface&gt;&gt;</p> <p style="text-align: center;">IpDataSessionControlManager</p>
<pre>enableDataSessionNotification(appInterface : in IpAppDataSessionControlManagerRef , eventCriteria : in TpDataSessionEventCriteria , assignmentID : out TpAssignmentIDRef) :TpResult disableDataSessionNotification(assignmentID : in TpAssignmentID) :TpResult</pre>

### 6.5.1.3 IpAppDataSession


<p style="text-align: center;">&lt;&lt;Interface&gt;&gt;</p> <p style="text-align: center;">IpAppDataSession</p>
<pre>connectRes(dataSessionID : in TpSessionID , eventReport : in TpDataSessionEventReport, assignmentID : in TpAssignmentID) :TpResult connectErr(dataSessionID : in TpSessionID , errorIndication : in TpDataSessionError, assignmentID : in TpAssignmentID) :TpResult superviseDataSessionRes(dataSessionID : in TpSessionID , report : in TpDataSessionSuperviseReport, usedVolume : in TpDataSessionSuperviseVolume) :TpResult superviseDataSessionErr(dataSessionID : in TpSessionID , errorIndication : in TpDataSessionError) :TpResult dataSessionFaultDetected(dataSessionID : in TpSessionID , fault : in TpDataSessionFault) :TpResult</pre>

### 6.5.1.4 IpDataSession

<<Interface>>
IpDataSession
connectReq(dataSessionID : in TpSessionID , responseRequested : in TpDataSessionReportRequestSet , targetAddress : in TpAddress , originatingAddress: in TpAddress, assignmentID : out TpAssignmentIDRef) : TpResult
release(dataSessionID : in TpSessionID , cause : in TpDataSessionReleaseCause) : TpResult
superviseDataSessionReq(dataSessionID : in TpSessionID, treatment : in TpDataSessionSuperviseTreatment , bytes : in TpDataSessionSuperviseVolume) : TpResult
setDataSessionChargePlan(dataSessionID: in TpSessionID, dataSessionChargePlan: in TpDataSessionChargePlan): TpResult
setAdviceOfCharge(dataSessionID : in TpSessionID, aoCInfo : in TpAoCInfo, tariffSwitch : in TpDuration): TpResult

## 6.6 Network User Location

The Network User Location (UL) SCF provides the `IpUserLocationCamel` interface, which provides methods for periodic and triggered location reporting. Most methods are asynchronous, in that they do not lock a thread into waiting whilst a transaction performs. In this way, the client machine can handle many more calls, than one that uses synchronous message calls. To handle responses and reports, the developer must implement `IpAppUserLocationCamel` interface to provide the callback mechanism.



**Figure 6-16:** Network User Location class diagram.


### 6.6.1 Network User Location SCF interface

This interface is the ‘SCF manager’ interface for Network User Location.

<<Interface>> IpUserLocationCamel
locationReportReq(appLocationCamel : in IpAppUserLocationCamelRef, users : in TpAddressSet, assignmentId : out TpSessionIDRef) : TpResult periodicLocationReportingStartReq(appLocationCamel : in IpAppUserLocationCamelRef, users : in TpAddressSet, reportingInterval : in TpDuration, assignmentId : out TpSessionIDRef) : TpResult periodicLocationReportingStop(stopRequest : in TpMobilityStopAssignmentData) : TpResult triggeredLocationReportingStartReq(appLocationCamel : in IpAppUserLocationCamelRef, users : in TpAddressSet, trigger : in TpLocationTriggerCamel, assignmentId : out TpSessionIDRef) : TpResult triggeredLocationReportingStop(stopRequest : in TpMobilityStopAssignmentData) : TpResult


## 6.6.2 Network User Location application interface

The network user location application interface is implemented by the client application developer and is used to handle location reports that are specific for mobile telephony users.



## 6.7 User Status


The User Status (US) SCF provides the `IpUserStatus` interface. Most methods are asynchronous, in that they do not lock a thread into waiting whilst a transaction performs. In this way, the client machine can handle many more calls, than one that uses synchronous message calls. To handle responses and reports, the developer must implement `IpAppUserStatus` interface to provide the callback mechanism.



**Figure 6-17:** User Status class diagram.


### 6.7.1 User Status SCF interface

The user status interface represents the interface to the user status service capability feature.




### 6.7.2 User Status application interface

The user-status application interface is implemented by the client application developer and is used to handle user status reports.




## 6.8 Terminal Capabilities

The Terminal Capabilities SCF enables the application to retrieve the terminal capabilities of the specified terminal. The Terminal Capabilities service provides a SCF interface that is called `IpTerminalCapabilities`. There is no need for an application interface, since `IpTerminalCapabilities` only contains the synchronous method `getTerminalCapabilities`.



**Figure 6-18: Terminal Capabilities package**



**Figure 6-19: Terminal Capabilities class diagrams**

### 6.8.1 Terminal Capabilities SCF interface

The Terminal Capabilities SCF interface `IpTerminalCapabilities` contains the synchronous method `getTerminalCapabilities`. The application has to provide the `terminalIdentity` is input to this method. The result indicates whether or not the terminal capabilities are available in the network and, in case they are, it will return the terminal capabilities (see the data definition of `TpTerminalCapabilities` for more information).


<code>&lt;&lt;Interface&gt;&gt;</code> <code>IpTerminalCapabilities</code>
<code>getTerminalCapabilities( terminalIdentity : in TpString,                            Result : out TpTerminalCapabilities) : TpResult</code>

## 7 State Transition Diagrams

This section contains the State Transition Diagrams for the objects that implement the interfaces on the gateway side. The State Transition Diagrams show the behaviour of these objects. For each state the methods that can be invoked by the application are shown. Methods not shown for a specific state are not relevant for that state and will return an exception. Apart from the methods that can be invoked by the application also events internal to the gateway or related to network events are shown together with the resulting event or action performed by the gateway. These internal events are shown between quotation marks.

### 7.1 Framework

#### 7.1.1 IpAuthentication



**Figure 7-1: State Transition Diagram for Authentication**

##### 7.1.1.1 Idle state

When the application has requested the **IpInitial** interface for **initiateAuthentication**, an object implementing the **IpAuthentication** interface is created. The application now has to provide its authentication capabilities by invoking the **SelectAuthMethod** method.

### 7.1.1.2 Init Authentication state

In this state the Framework selects the preferred authentication mechanism within the capability of the application. When a proper mechanism is found, the Framework can decide that the application doesn't have to be authenticated (one way authentication) or that the application has to be authenticated. In case no mechanism can be found the error code P\_INVALID\_AUTH\_CAPABILITY is returned and the Authentication object is destroyed. This implies that the application has to re-initiate the authentication by calling once more the initiateAuthentication method on the IpInitial interface.


### 7.1.1.3 Wait For Application Result state

When entering this state, the Framework requests the application to authenticate itself by invoking the Authenticate method on the application. In case the application requests the Framework to authenticate itself by invoking Authenticate on the IpAuthentication interface, the Framework provides the correct response to the challenge of the application. When the Framework responds to the Authenticate request, the response is analysed and in case the response is valid a transition to the state Application Authenticated is made. In case the response is not valid, the Authentication object is destroyed. This implicates that the application has to re-initiate the authentication by calling once more the initiateAuthentication method on the IpInitial interface.

### 7.1.1.4 Application Authenticated state

In this state the application is considered authenticated and is now allowed to request access to the IpAccess interface. In case the application requests the Framework to authenticate itself by invoking Authenticate on the IpAuthentication interface, the Framework provides the correct response to the challenge of the application.

## 7.1.2 IpAccess




**Figure 7-2: State Transition Diagram for Access**

### 7.1.2.1 Active state

When the application requestes access to the Framework on the IpInitial interface, an object implementing the IpAccess interface is created. The application can now request other Framework interfaces, including Service Discovery. When the application is no longer interested in using the interfaces it calls the endAccess method. This results in the destruction of all interface objects used by the application. In case the network operator decides that the application has no longer access to the interfaces the same will happen.

### 7.1.3 IpServiceDiscovery




**Figure 7-3: State Transition Diagram for Service Discovery**

#### 7.1.3.1 Active state

When the application requests for the Service Discovery SCF by invoking the obtainInterface or the obtainInterfaceWithCallback methods on the IpAccess interface, an instance of the IpServiceDiscovery will be created. Next the application is allowed to request a list of the provided SCFs and to obtain a reference to interfaces of SCFs.

## 7.1.4 IpLoadManager



**Figure 7-4: State Transition Diagram for LoadManager**

### 7.1.4.1 Idle State

In this state the application has obtained an interface reference of the LoadManager from the IpAccess interface.

### 7.1.4.2 Registered State

In this state the application has registered for load control with the method `RegisterLoadController()`. The LoadManager can now request the application to supply load statistics information (by invoking `queryAppLoadReq()`). Furthermore the LoadManager can request the application to control its load (by invoking `enableLoadControl()` or `suspendNotification()` on the application side of interface). In case the application detects a change in load level, it reports this to the LoadManager by calling the method `reportLoad()`.


When entering this state, an object called `LoadManagerInternal` is created that has an internal state machine encapsulating the internal behaviour of the LoadManager. The State Transition Diagram of `LoadManagerInternal` is shown in Figure .

### 7.1.4.3 Notifying

In the Notifying state the application has requested for load statistics. The Loadmanager gathers the requested information and (periodically) reports them to the application.

### 7.1.4.4 Suspending Notification

Due to e.g. a temporary load condition, the application has requested the LoadManager to suspend sending the load statistics information.



**Figure 7-5: State Transition Diagram for the LoadManagerInternal**

### 7.1.4.5 Normal Load state

In this state the none of the entities defined in the load balancing policy between the application and the framework / SCFs is overloaded.

### 7.1.4.6 Application overload state

In this state the application has indicated it is overloaded. When entering this state the load policy is consulted and the appropriate actions are taken by the LoadManager.

### 7.1.4.7 Internal overload

In this state the Framework or one or more of the SCFs within the specific load policy is overloaded. When entering this state the load policy is consulted and the appropriate actions are taken by the LoadManager.

### 7.1.4.8 Internal and application overload

In this state the application is overloaded as well as the Framework or one or more of the SCFs within the specific load policy. When entering this state the load policy is consulted and the appropriate actions are taken by the LoadManager.

## 7.1.5 IPFaultManager




Figure 7-6: State Transition Diagram for Fault Manager

### 7.1.5.1 Framework Active state

This is the normal state of the framework, which is fully functional and able to handle requests from both applications and services capability features.

### 7.1.5.2 Framework Faulty state

In this state, the framework has detected an internal problem with itself such that application and services capability features cannot communicate with it anymore; attempts to invoke any methods that belongs to any SCFs of the framework returns an error. If the framework ever recover, application with fault management callbacks will be notified via a fwFaultRecoveryInd message.


### 7.1.5.3 The Service Activity Test state

In this state, the framework is performing a test on one service capability feature. If the SCF is faulty, applications with fault management callbacks are notified accordingly through a svcUnavailableInd message.

### 7.1.5.4 The Framework Activity Test state

In this state, the framework is performing self-diagnostic test. If a problem is diagnosed, all applications with fault management callbacks are notified through a fwFaultReportInd message.

## 7.1.6 IpHeartbeatmgmt



**Figure 7-7: State Transition Diagram for the Heartbeat manager**


### 7.1.6.1 Application not supervised

In this state the application has not registered for heartbeat supervision by the Framework.

### 7.1.6.2 Application supervised

In this state the application has registered for heartbeat supervision by the Framework. Periodically the Framework will request for the application heartbeat by calling the send method on the `IpAppHeartBeat` interface.

### 7.1.7 IpHeartBeat




**Figure 7-8: State Transition Diagram for HeartBeat**

#### 7.1.7.1 FW Supervised by Application state

In this state the Framework has requested the application for heartbeat supervision on itself. Periodically the application calls the send() method and the Framework returns its heartbeat result.

### 7.1.8 IpOAM




**Figure 7-9: State Transition Diagram for OAM**

### 7.1.8.1 Active state

In this state the application has obtained a reference to the IpOAM interface. The application is now able to request the date / time of the Framework.

### 7.1.9. IpServiceRegistration



**Figure 7-10: State Transition Diagram for Service Registration**

#### 7.1.9.1 Registering SCF


This is the state entered when a Service Capability Server (SCS) starts the registration of its SCF in the Framework, by informing it of the existence of an SCF characterised by a service type and a set of service properties. As a result the Framework associates a service ID to this SCF, that will be used to identify it by both sides. When receiving this ID, the SCS instantiates a manager interface for this SCF, which will be the entry point for applications that want to use it.

#### 7.1.9.2 SCF Registered

This is the state entered when, the service manager interface having been instantiated, the SCS informs the Framework of the availability of the SCF, and makes it actually available by providing the Framework with the manager interfaces to be used by applications. Anytime the SCF availability may be withdrawn by un-registering it.

## 7.2 Generic Call Control

### 7.2.1 Call Control Manager



**Figure 7-11: State Transition Diagram for the CallControlManager**


#### 7.2.1.1 Active state

In this state a relation between the Application and the Generic Call Control Service Capability Feature has been established. It allows the application to indicate that it is interested in call related events. In case such an event occurs, the Call Control Manager will create a Call object and inform the application by invoking the method `callEventNotify()` on the `IpAppCallControlManager` interface. The application can also indicate it is no longer interested in certain call related events by calling `disableCallNotification()`.

#### 7.2.1.2 Notification terminated state

When the Call Control manager is in the Notification terminated state, events requested with `enableCallNotification()` will not be forwarded to the application. There can be multiple reasons for this: for instance it might be that the application receives more notifications than defined in the Service Level Agreement. Another example is that the SCS has detected it receives no notifications from the network due to e.g. a link failure. In this state no requests for new notifications will be accepted.

### 7.2.2 Call



**Figure 7-12: State Transition Diagram for Call**

### 7.2.2.1 Active state

In this state a call between two parties is being setup or present. Refer to the substates for more details

The application can request the gateway for a certain type of charging of the call by calling `setCallChargePlan()`. The application can request for charging related information by calling `getCallInfoReq()`. Furthermore the application can request supervision of the call by calling `superviseCallReq()`. It is also allowed to send Advice Of Charge information by calling `setAdviceOfCharge()`.

#### 7.2.2.1.1 1 Party in Call state

When the Call is in this state a calling party is present. The application can now request that a connection to a called party be established by calling the method routeReq(). When the calling party abandons the call before the application has invoked the routeReq() operation, the gateway informs the application by invoking callFaultDetected() and also the operation callEnded() will be invoked. When the calling party abandons the call after the application has invoked

routeReq() but before the call has actually been established, the gateway informs the application by invoking callEnded().

When the calling party answers the call, a transition will be made to the 2 Parties in Call state. In case the call can not be established because the application supplied an invalid address or the connection to the called party was unsuccessful while the application was monitoring for the latter in interrupt mode, the Call object will stay in this state

In this state user interaction is possible unless there is an outstanding routing request.

### 7.2.2.1.2 2 Parties in Call state

A connection between two parties has been established.

In case the calling party disconnects, the gateway informs the application by invoking callEnded().

When the called party disconnects different situations apply:

1. the application is monitoring for this event in interrupt mode: a transition is made to the 1 Party in Call state, the application is informed with routeRes with indication that the called party has disconnected and all requested reports are sent to the application. The application now again has control of the call.
2. the application is monitoring for this event but not in interrupt mode. In this case a transition is made to the Network Released state and the gateway informs the application by invoking the operation routeRes() and callEnded().
3. the application is not monitoring for this event. In this case the application is informed by the gateway invoking the callEnded() operation and a transition is made to the Network Released state.

In this state user interaction is possible, but only when the application requested to be notified of the transition to this state in interrupt mode. After the user interaction is finished the gateway will automatically continue processing of the call.

### 7.2.2.3 Network released state

In this state the call has ended and the Gateway collects the possible call information requested with getCallInfoReq() and / or superviseCallReq(). The information will be returned to the application by invoking the methods getCallInfoRes() and / or superviseCallRes() on the application. Also when a call was unsuccessful these methods are used. In case the application has not requested additional call related information immediately a transition is made to state Idle.

### 7.2.2.4 Finished state

In this state the call has ended and no call related information is to be send to the application. The application can only release the Call object. Calling the deassingCall() method has the same effect. Note that the application has to release the object itself as good OO practice requires that when an object was created on behalf of a certain entity, this entity is also responsible for destroying it when the object is no longer needed.


### 7.2.2.5 Application released state.

In this state the application has requested to release the Call object and the Gateway collects the possible call information requested with getCallInfoReq(). In case the application has not requested additional call related information immediately the Call object is destroyed.

## 7.3 User Interaction

### 7.3.1 UI Manager

"arrival of user initiated request for user interaction" [ notification active for this ui event ] / create a UI object ^IpAppUIManager.userInteractionEventNotify



**Figure 7-13: State Transition Diagram for the UIManager**


#### 7.3.1.1 Active state

In this state a relation between the Application and a User Interaction Service Capability Feature (Generic User Interaction or Call User Interaction) has been established. The application is now able to request creation of UI and/or UICall objects.

#### 7.3.1.2 Notification Terminated state

When the UI manager is in the Notification terminated state, events requested with enableUINotification() will not be forwarded to the application. There can be multiple reasons for this: for instance it might be that the application receives more notifications than defined in the Service Level Agreement. Another example is that the SCS has detected it receives no notifications from the network due to e.g. a link failure. In this state no requests for new notifications will be accepted.

### 7.3.2 UI



**Figure 7-14: State Transition Diagram for UI**

#### 7.3.2.1 Active state

In this state the UI object is available for requesting messages to be send to the network.

#### 7.3.2.2 Release Pending state

A transition to this state is made when the Application has indicated that after a certain message no further messages need to be send to the end-user. There are, however, still a number of messages that are not yet completed. When the last message is sent or when the last user interaction has been obtained, the UI object is destroyed.

### 7.3.3 UI Call




Figure 7-15: State Transition Diagram for UICall


#### 7.3.3.1 Active state

In this state a UICall object is available for announcements to be played to an end-user or obtaining information from the end-user.

#### 7.3.3.2 Release Pending state

A transition to this state is made when the Application has indicated that after a certain announcement no further announcements need to be played to the end-user. There are, however, still a number of announcements that are not yet completed. When the last announcement is played or when the last user interaction has been obtained, the UICall object is destroyed.

## 7.4 Data Session



**Figure 7-16: State Transition Diagram for Data Session**

### 7.4.1 Active state

In this state a data connection between two parties is being setup or established (refer to the substates for more details). The application can request the gateway for a certain type of charging by calling `setDataSessionChargePlan()`, send advice of charge information by calling `setAdviceOfCharge()`, and request supervision of the data session by calling `superviseDataSessionReq()`.

#### 7.4.1.1 Setup state

The Setup state is reached after a `dataSessionEventNotify()` indicates to the application that a data session is interested in being connected. If the application is going to connect the two parties by invoking `connectReq()` it may call the charging or supervision methods before.

#### 7.4.1.2 Established state

In this state the data connection is established. If supervision has been requested the application expects the corresponding `superviseDataSessionRes()`.

### 7.4.2 Network Released state

In this state the data session has ended. In the case on a normal user disconnection the transition to this state is indicated to the application by the disconnect report of connectRes(). But this will only happen if the application requested monitoring of the disconnect event before. An abnormal disconnection is indicated by dataSessionFaultDetected(). The application may wait for outstanding superviseDataSessionRes().


### 7.4.3 Finished state

In this state the data session has ended and no further data session related information is to be send to the application. The application can only release the data session object. If the application fails to invoke release() within a certain period of time the gateway should automatically release the object and send a timeout indication to the application.

### 7.4.4 Application released state.

In this state the application has released the data session object. If supervision has been requested the gateway will collect the information and send superviseDataRes() to the application.

## 7.5 Network User Location




**Figure 7-17: State Transition Diagram for Network User Location**

During the signServiceAgreement a new user location interface reference is created, which is user as the initial point of contact for the application.

### 7.5.1 Active state

In this state, a relation between the Application and the Network User Location Service Capability Feature has been established. It allows the application to request a specific user location reports, subscribe to periodic user location reports or subscribe to triggers that generate location report when a location update occurs inside the current VLR area or when the user moves to another VLR area or both.

## 7.6 User Status



**Figure 7-18: State Transition Diagram for User Status.**

## 7.6.1 Active State

In this state, a relation between the Application and the User Status Service Capability Feature has been established. It allows the application to request a specific user status report or subscribe to triggers that generate status reports when the status of one of the monitored user changes.

# 8 Data Definitions

## 8.1 Common Data definitions

The constants and types defined in the following sections are defined in the *org.threegpp.osa* package.

### 8.1.1 Primitive Data Types

Type Name	Description
TpBoolean	Defines a Boolean data type.
TpInt32	Defines a signed 32 bit integer.
TpFloat	Defines a single precision float
TpString	Defines a string, comprising length and data.

### 8.1.2 Structured data types classification

Many different structured data types are used in OSA and a classification/clarification is required.

#### 8.1.2.1 Structures made of data elements

This describes data types that can be considered as classes (in Java or C++) or structures (C++, IDL). The goal of these data types is to group pieces of information into a logical unit. *Example:* an TAddress data type may be defined in IDL as:

```
struct TpAddress {
    TpAddressPlan      Plan;
    TpString           AddrString;
    TpString           Name;
    TpAddressPresentation Presentation;
    TpAddressScreening Screening;
    TpString           SubAddressString;
};
```

#### 8.1.2.2 Tagged choice of data elements (i.e.: Free unions)

This describes a data type, which actually evaluates to one of a choice of a number of data elements. This data element contains two parts: a tag data type (the *tag* part) which is used to identify the chosen data type, and the chosen data type itself (the *union* part). This form of data type is also referred to as a tagged union.

This data type can be implemented in IDL as a union with a switch statement for the *tag* part, and a set or case statements for the *union* part.

*Example:* The TCallError data type may be defined in IDL as:

```
union TpCallError switch (TCallErrorHandlerType) {
    case CALL_ERROR_UNDEFINED:
```

```

TpCallErrorInfoDefault           CallErrorUndefined;

case CALL_ERROR_ROUTING_ABORTED: CallErrorRoutingAborted;

case CALL_ERROR_CALL_ABANDONED:  CallErrorCallAbandoned;

case CALL_ERROR_INVALID_ADDRESS: CallErrorInvalidAddress;

case CALL_ERROR_INVALID_STATE:   CallErrorInvalidState;

case CALL_ERROR_INVALID_CRITERIA: CallErrorInvalidCriteria;

TpCallErrorInfoDefault           CallErrorDefault;
};

}

```

### 8.1.2.3 Collection of data elements

This describes a data type, which comprises an ordered or unordered collection of data elements of the same type. The number of data elements in the collection is always known and can be implicit (IDL) or may appear as an integer inside a structure depending on the language used. This data type can be implemented in IDL as a sequence.

*Example:*

```
typedef sequence<SessionID> SessionIDSet;
```

### 8.1.2.4 References

This describes a reference (or pointer) to a data type. This is primarily used to describe 'out' method parameters.

This data type may be implemented (for example, in C++) as a pointer. However, in some languages it may not be necessary for 'out' parameters to be implemented as pointers.

*Example:* The TAddressRef data type may be defined in C++ as:

```
typedef TAddress *TAddressRef;
```

## 8.1.3 Interface Definitions

### 8.1.3.1 IpOsa

Defines the address of an IpOsa Interface.

### 8.1.3.2 IpOsaRef

Defines a Reference to type IpOsa

### 8.1.3.3 IpOsaRefRef

Defines a Reference to type IpOsaRef

### 8.1.3.4 IpService

Defines the address of an IpService Interface.

### 8.1.3.5 IpServiceRef

Defines a Reference to type IpService

### 8.1.3.6 IpServiceRefRef

Defines a Reference to type IpServiceRef

## 8.1.4 Non primitive and structured type types definition

### 8.1.4.1 TpAssignmentID

This data type is identical to a TpInt32. It specifies a number which identifies an individual event notification enabled by the application or OSA service capability feature.

### 8.1.4.2 TpSessionID

Defines a network unique session ID. OSA uses this ID to identify sessions within an object implementing an interface capable of handling multiple sessions. For the different OSA service capability features, the sessionIDs are unique only in the context of a manager instantiation (e.g., within the context of one generic call control manager). As such if an application creates two instances of the same SCF manager it shall use different instantiations of the callback objects which implement the callback interfaces.

The session ID is identical to a TpInt32 type.

### 8.1.4.3 TpSessionIDSet

Defines a collection of data elements of TpSessionID.

### 8.1.4.4 TpDuration

This data type is a TpInt32 representing a time interval in milliseconds. A value of "-1" defines infinite duration and value of "-2" represents default duration.

### 8.1.4.5 TpResult

Defines the structure of data elements that specifies the result of a method call.

Structure Member Name	Structure Member Type
ResultType	TpResultType
ResultFacility	TpResultFacility
ResultInfo	TpResultInfo

### 8.1.4.6 TpResultType

Defines whether the method was successful or not.

Name	Value	Description
P_RESULT_FAILURE	0	Method failed
P_RESULT_SUCCESS	1	Method was successful

### 8.1.4.7 TpResultFacility

Defines the facility code of a result. In Release 99 of the OSA API, only P\_RESULT\_FACILITY\_UNDEFINED must be used.

Name	Value	Description
P_RESULT_FACILITY_UNDEFINED	0	Undefined

### 8.1.4.8 TpResultInfo

Defines further information relating to the result of the method, such as error codes.

Name	Value	Description
P_RESULT_INFO_UNDEFINED	0000h	No further information present
P_INVALID_APPLICATION_ID	0001h	Invalid application ID
P_INVALID_CLIENT_CAPABILITY	0002h	Invalid client capability
P_INVALID_AGREEMENT_TEXT	0003h	Invalid agreement text
P_INVALID_SIGNING_ALGORITHM	0004h	Invalid signing algorithm
P_INVALID_INTERFACE_ID	0005h	Invalid interface ID
P_INVALID_SERVICE_ID	0006h	Invalid service capability feature ID
P_INVALID_EVENT_TYPE	0007h	Invalid event type
P_SERVICE_NOT_ENABLED	0008h	The service capability feature ID does not correspond to a SCF that has been enabled
P_INVALID_ASSIGNMENT_ID	0009h	The assignment ID does not correspond to one of the valid assignment IDs
P_INVALID_PARAMETER	000Ah	The method has been called with an invalid parameter
P_INVALID_PARAMETER_VALUE	000Bh	A method parameter has an invalid value
P_PARAMETER_MISSING	000Ch	A required parameter has not been specified in the method call
P_RESOURCES_UNAVAILABLE	000Dh	The required resources in the network are not available
P_TASK_REFUSED	000Eh	The requested method has been refused
P_TASK_CANCELLED	000Fh	The requested method has been cancelled
P_INVALID_DATE_TIME_FORMAT	0010h	Invalid date and time format provided
P_NO_CALLBACK_ADDRESS_SET	0011h	The requested method has been refused because no callback address is set
P_INVALID_TERMINATION_TEXT	0012h	Invalid termination text
P_INVALID_SERVICE_TOKEN	0013h	The service capability feature token does not correspond to a token that had been issued, or the issued token has expired
P_INVALID_AUTHENTICATION	0014h	The client has not been correctly authenticated
P_INVALID_SERVICE_PROPERTY	0015h	Invalid service capability feature property
P_METHOD_NOT_SUPPORTED	001Bh	The method is not allowed or supported within the context of the current SCF agreement.
General security errors		
P_USER_NOT_SUBSCRIBED	0030h	A service (or application) is unauthorised to access information and request SCFs with regards to users that are <b>not</b> subscribed to it.
P_APPLICATION_NOT_ACTIVATED	0031h	A service (or application) is unauthorised to access information and request SCFs with regards to its subscribed users that have <b>deactivated</b> that particular service (or application).
P_USER_PRIVACY	0032h	A service (or application) is unauthorised to access information and request an SCF with regards to its subscribed users that have <b>set</b> their privacy flag regarding that particular SCF.
P_GCCS_SERVICE_INFORMATION_MISSING	0100h	Information relating to the Call Control SCF could not be found
P_GCCS_SERVICE_FAULT_ENCOUNTERED	0101h	Fault detected in the Call Control SCF
P_GCCS_UNEXPECTED_SEQUENCE	0102h	Unexpected sequence of methods, i.e., the sequence does not match

		the specified state diagrams for the call or the call leg.
P_GCCS_INVALID_ADDRESS	0103h	Invalid address specified
P_GCCS_INVALID_CRITERIA	0105h	Invalid criteria specified
P_GCCS_INVALID_NETWORK_STATE	0106h	Although the sequence of method calls is allowed by the OSA gateway, the underlying protocol can not support it. E.g., in some protocols some methods are only allowed by the protocol, when the call processing is suspended, e.g., after reporting an event that was monitored in interrupt mode.
P_GUIS_INVALID_CRITERIA	0300h	Invalid criteria specified
P_GUIS_ILLEGAL_ID	0301h	Information id specified is invalid
P_GUIS_ID_NOT_FOUND	0302h	A legal information id is not known to the User Interaction SCF
P_GUIS_ILLEGAL_RANGE	0303h	The values for minimum and maximum collection length are out of range.
P_GUIS_INVALID_COLLECTION_CRITERIA	0304h	Invalid collection criteria specified
P_GUIS_INVALID_NETWORK_STATE	0306h	Although the sequence of method calls is allowed by the OSA gateway, the underlying protocol can not support it. E.g., in some protocols some methods are only allowed by the protocol, when the call processing is suspended, e.g., after reporting an event that was monitored in interrupt mode.
P_GUIS_UNEXPECTED_SEQUENCE	0307h	Unexpected sequence of methods, i.e., the sequence does not match the specified state diagrams.
P_DSCS_SERVICE_INFORMATION_MISSING	0400h	Information relating to the Data Session Control SCF could not be found
P_DSCS_SERVICE_FAULT_ENCOUNTERED	0401h	Fault detected in the Data Session Control SCF
P_DSCS_UNEXPECTED_SEQUENCE	0402h	Unexpected sequence of methods, i.e., the sequence does not match the specified state diagrams for the data session.
P_DSCS_INVALID_ADDRESS	0403h	Invalid address specified
P_DSCS_INVALID_STATE	0404h	Invalid state specified
P_DSCS_INVALID_CRITERIA	0405h	Invalid criteria specified
P_DSCS_INVALID_NETWORK_STATE	0406h	Although the sequence of method calls is allowed by the OSA gateway, the underlying protocol can not support it.

#### 8.1.4.9 TpDate

This data type is identical to a TpString. It specifies the data in accordance with International Standard ISO 8601. This is defined as the string of characters in the following format:

**YYYY-MM-DD**

where the date is specified as:

<b>YYYY</b>	<b>four digits year</b>
<b>MM</b>	<b>two digits month</b>
<b>DD</b>	<b>two digits day</b>

The date elements are separated by a hyphen character (-).

**Example:**

The 4 December 1998, is encoded as the string:

**1998-12-04**

### 8.1.4.10 TpTime

This data type is identical to a TpString. It specifies the time in accordance with International Standard ISO 8601. This is defined as the string of characters in the following format:

**HH:MM:SS.mmm**

or

**HH:MM:SS.mmmZ**

where the time is specified as:

<b>HH</b>	<b>two digits hours (24h notation)</b>
<b>MM</b>	<b>two digits minutes</b>
<b>SS</b>	<b>two digits seconds</b>
<b>mmm</b>	<b>three digits fractions of a second (i.e. milliseconds)</b>

The time elements are separated by a colon character (:). The date and time are separated by a space. Optionally, a capital letter Z may be appended to the time field to indicate Universal Time (UTC). Otherwise, local time is assumed.

*Example*

For local time, 10:30 and 15 seconds is encoded as the string:

**10:30:15.000**

or in UTC it would be:

**10:30:15.000Z**

### 8.1.4.11 TpDateAndTime

This data type is identical to a TpString. It specifies the data and time in accordance with International Standard ISO 8601. This is defined as the string of characters in the following format:

**HH:MM:SS.mmm**

or

**YYYY-MM-DD HH:MM:SS.mmmZ**

where the date is specified as:

<b>YYYY</b>	<b>four digits year</b>
<b>MM</b>	<b>two digits month</b>
<b>DD</b>	<b>two digits day</b>

The date elements are separated by a hyphen character (-).

The time is specified as:

<b>HH</b>	<b>two digits hours (24h notation)</b>
<b>MM</b>	<b>two digits minutes</b>
<b>SS</b>	<b>two digits seconds</b>
<b>mmm</b>	<b>three digits fractions of a second (i.e. milliseconds)</b>

A colon character separates the time elements (:). The date and time are separated by a space. Optionally, a capital letter Z may be appended to the time field to indicate Universal Time (UTC). Otherwise, local time is assumed.

*Example*

The 4 December 1998, at 10:30 and 15 seconds is encoded as the string:

**10:30:15.000**

for local time, or in UTC it would be:

**10:30:15.000Z**

### 8.1.4.12 TpAddress

Defines the structure of data elements that specifies an address.

Structure Member Name	Structure Member Type
Plan	TpAddressPlan
AddrString	TpString
Name	TpString
Presentation	TpAddressPresentation
Screening	TpAddressScreening
SubAddressString	TpString

### 8.1.4.13 TpAddressSet

Defines a collection of TpAddress elements.

### 8.1.4.14 TpAddressPlan

Defines the address plan (or numbering plan) used. It is also used to indicate whether an address is actually defined in a Address data element.

Name	Value	Description
P_ADDRESS_PLAN_NOT_PRESENT	-1	No Address Present
P_ADDRESS_PLAN_UNDEFINED	0	Undefined
P_ADDRESS_PLAN_IP	1	IP
P_ADDRESS_PLAN_MULTICAST	2	Multicast
P_ADDRESS_PLAN_UNICAST	3	Unicast
P_ADDRESS_PLAN_E164	4	E.164
P_ADDRESS_PLAN_E164_MOBILE	5	E.164 Mobile
P_ADDRESS_PLAN_AESA	6	AESA
P_ADDRESS_PLAN_URL	7	URL
P_ADDRESS_PLAN_NSAP	8	NSAP
P_ADDRESS_PLAN_SMBTP	9	SMTP
P_ADDRESS_PLAN_X400	11	X.400

### 8.1.4.15 TpAddressPresentation

Defines whether an address can be presented to an end user.

Name	Value	Description
P_ADDRESS_PRESENTATION_UNDEFINED	0	Undefined
P_ADDRESS_PRESENTATION_ALLOWED	1	Presentation Allowed
P_ADDRESS_PRESENTATION_RESTRICTED	2	Presentation Restricted
P_ADDRESS_PRESENTATION_ADDRESS_NOT_AVAILABLE	3	Address not available for presentation

### 8.1.4.16 TpAddressRange

This type is identical to TpAddress with the difference that the AddrString can contain wildcards.

Two wildcards are allowed: \* which matches zero or more characters and ? which matches exactly one character. The wildcards are only allowed at the end or at the beginning of the addrString.

Some examples for E164 addresses:

- “123” matches specified number.
- “123\*” matches all numbers starting with 123 (including 123 itself).
- “123??\*” matches all numbers starting with 123 and at least 5 digits long.
- “123???” matches all numbers starting with 123 and exactly 6 digits long

For e-mail style addresses, the wildcards can be used at the beginning of the addrString:

- \*@3gpp.org matches all email addresses in the 3gpp.org domain.

The following address ranges are illegal:

- 1?3
- 1\*3
- ?123\*

### 8.1.4.17 TpAddressScreening

Defines whether an address has been screened by the application.

Name	Value	Description
P_ADDRESS_SCREENING_UNDEFINED	0	Undefined
P_ADDRESS_SCREENING_USER_VERIFIED_PASSED	1	user provided address verified and passed
P_ADDRESS_SCREENING_USER_NOT_VERIFIED	2	user provided address not verified
P_ADDRESS_SCREENING_USER_VERIFIED_FAILED	3	user provided address verified and failed
P_ADDRESS_SCREENING_NETWORK	4	Network provided address

### 8.1.4.18 TpAddressError

Defines the reasons why an address is invalid.

Name	Value	Description
P_ADDRESS_INVALID_UNDEFINED	0	Undefined error
P_ADDRESS_INVALID_MISSING	1	Mandatory address not present
P_ADDRESS_INVALID_MISSING_ELEMENT	2	Mandatory address element not present
P_ADDRESS_INVALID_OUT_OF_RANGE	3	Address is outside of the valid range
P_ADDRESS_INVALID_INCOMPLETE	4	Address is incomplete
P_ADDRESS_INVALID_CANNOT_DECODE	5	Address cannot be decoded

### 8.1.4.19 TpURL

This data type is identical to a TpString and contains a URL address. The usage of this type is distinct of TpAddress, which can also hold an URL. The latter contains a user address which can be specified in many ways: IP, mail, URL, X.300, E164. On the other hand, the TpURL type does not hold the address of a user and always represents a URL. This type is used in user interaction and defines the URL of the text or stream to be sent to an end-user. It is therefore inappropriate to use a general address here.

### 8.1.4.20 TpPrice

This data type is identical to a TpString. It specifies price information, which is used in user interaction when an announcement is being played and additional information is given to the user. This is defined as the string of characters (digits) in the following format:

**DDDDDD.DD**

### 8.1.4.21 TpAoCInfo

Defines the Sequence of Data Elements that specify the Advice Of Charge information to be sent to the terminal.

Sequence Element Name	Sequence Element Type	Description
ChargeOrder	TpAoCOrder	Charge order
Currency	TpString	Currency unit according to ISO-4217:1995

### 8.1.4.22 TpAoCOrder

Defines the Tagged Choice of Data Elements that specify the charge plan for the call.

	Tag Element Type	
	TpAoCOrderCategory	

Tag Element Value	Choice Element Type	Choice Element Name
P_CHARGE_ADVICE_INFO	TpChargeAdviceInfo	ChargeAdviceInfo
P_CHARGE_PER_TIME	TpChargePerTime	ChargePerTime
P_CHARGE_NETWORK	TpString	NetworkCharge

### 8.1.4.23 TpCallAoCOrderCategory

Name	Value	Description
P_CHARGE_ADVICE_INFO	0	Set of GSM Charge Advice Information elements according to 3G TS 22.024
P_CHARGE_PER_TIME	1	Charge per time
P_CHARGE_NETWORK	2	Operator specific charge plan specification, e.g. charging table name / charging table entry

### 8.1.4.24 TpChargeAdviceInfo

Defines the Sequence of Data Elements that specify the two sets of Advice of Charge parameters. The first set defines the current tariff. The second set may be used in case of a tariff switch in the network.

Sequence Element Name	Sequence Element Type	Description
CurrentCAI	TpCAIElements	Current tariff
NextCAI	TpCAIElements	Next tariff after tariff switch

#### 8.1.4.25 TpCAIElements

Defines the Sequence of Data Elements that specify the Charging Advice Information elements according to 3G TS 22.024.

Sequence Element Name	Sequence Element Type	Description
UnitsPerInterval	TpInt32	Units per interval
SecondsPerTimeInterval	TpInt32	Seconds per time interval
ScalingFactor	TpInt32	Scaling factor
UnitIncrement	TpInt32	Unit increment
UnitsPerDataInterval	TpInt32	Units per data interval
SegmentsPerDataInterval	TpInt32	Segments per data interval
InitialSecsPerTimeInterval	TpInt32	Initial secs per time interval

#### 8.1.4.26 TpChargePerTime

Defines the Sequence of Data Elements that specify the time based charging information.

Sequence Element Name	Sequence Element Type	Description
InitialCharge	TpInt32	Initial charge amount (in currency units * 0.0001)
CurrentChargePerMinute	TpInt32	Current tariff (in currency units * 0.0001)
NextChargePerMinute	TpInt32	Next tariff (in currency units * 0.0001) after tariff switch Only used in setAdviceOfCharge()

## 8.2 Framework Data Definitions

This section provides the framework specific data definitions necessary to support the OSA interface specification.

This document is written using Hypertext link, to aid navigation through the data structures. Underlined text represents Hypertext links.

The general format of a data definition specification is the following:

- Data type, that shows the name of the data type.
- Description, that describes the data type.
- Tabular specification, that specifies the data types and values of the data type.
- Example, if relevant, shown to illustrate the data type.

### 8.2.1 Common Framework Data Definitions

#### 8.2.1.1 TpClientApplID

This is an identifier for the client application. It is used to identify the client to the framework. This data type is identical to TpString and is defined as a string of characters that uniquely identifies the application. The content of this

string shall be unique for each OSA API implementation (or unique for a network operator's domain). This unique identifier shall be negotiated with the OSA operator and the application shall use it to identify itself.

### 8.2.1.2 TpClientAppIDList

This data type defines a Numbered Set of Data Elements of type TpClientAppID.

### 8.2.1.3 TpEntOpID

This data type is identical to TpString and is defined as a string of characters that identifies an enterprise operator. In conjunction with the application it uniquely identifies the enterprise operator which uses a particular OSA Service Capability Feature.

### 8.2.1.4 TpEntOpIDList

This data type defines a Numbered Set of Data Elements of type TpEntOpID.

### 8.2.1.5 TpService

This data type is a Sequence of Data Elements which describes a registered SCFs. It is a structured type which consists of:

Sequence Element Name	Sequence Element Type	Documentation
ServiceID	TpServiceID	
ServicePropertyList	TpServicePropertyList	

### 8.2.1.6 TpServiceList

This data type defines a Numbered Set of Data Elements of type TpService.

### 8.2.1.7 TpServiceDescription

This data type is a Sequence of Data Elements which describes a registered SCF. It is a structured data type which consists of:

Sequence Element Name	Sequence Element Type	Documentation
ServiceTypeName	TpServiceTypeName	
ServicePropertyList	TpServicePropertyList	

### 8.2.1.8 TpServiceID

This data type is identical to a TpString, and is defined as a string of characters that uniquely identifies an instance of a SCF interface. The string is automatically generated by the Framework, and comprises a TpUniqueServiceNumber, TpServiceNameString, and a number of relevant TpServiceSpecString, which are concatenated using a forward separator (/) as the separation character.

### 8.2.1.9 TpServiceIDList

This data type defines a Numbered Set of Data Elements of type TpServiceID.

### 8.2.1.10 TpServiceIDRef

Defines a Reference to type TpServiceId.

### 8.2.1.11 TpServiceNameString

This data type is identical to a TpString, and is defined as a string of characters that uniquely identifies the name of an SCF interface. Other Network operator specific capabilities may also be used, but should be preceded by the string "SP\_".The following values are defined for OSA release 99.

Character String Value	Description
NULL	An empty (NULL) string indicates no SCF name
P_CALL_CONTROL	The name of the Call Control SCF
P_USER_INTERACTION	The name of the User Interaction SCFs
P_TERMINAL_CAPABILITIES	The name of the Terminal Capabilities SCF
P_USER_LOCATION	The name of the Network User Location SCF
P_USER_STATUS	The name of the User Status SCF
P_DATA_SESSION_CONTROL	The name of the Data Session Control SCF

### 8.2.1.12 TpServiceSpecString

This data type is identical to a TpString, and is defined as a string of characters that uniquely identifies the name of an SCF specialisation interface. Other network operator specific capabilities may also be used, but should be preceded by the string "SP\_".The following values are defined for OSA release 99.

Character String Value	Description
NULL	An empty (NULL) string indicates no SCF specialisation
P_CALL	The Call specialisation of the of the User Interaction SCF

### 8.2.1.13 TpUniqueServiceNumber

This data type is identical to a TpString, and is defined as a string of characters that represents a unique number that is used to build the service ID (refer to TpServiceID).

### 8.2.1.14 TpPropertyStruct

This data type is a Sequence of Data Elements which describes an SCF property. It consists of:

Sequence Element Name	Sequence Element Type	Documentation
ServicePropertyName	TpServiceTypeName	
ServicePropertyMode	TpServicePropertyMode	
ServicePropertyTypeName	TpServicePropertyTypeName	

### 8.2.1.15 TpPropertyStructList

This data type defines a Numbered Set of Data Elements of type TpPropertyStruct.

### 8.2.1.16 TpServicePropertyMode

This type is left as a placeholder but is not used in release 99. This defines SCF property modes.

Name	Value	Documentation
NORMAL	0	The value of the corresponding SCF property type may optionally be provided
MANDATORY	1	The value of the corresponding SCF property type must be provided at service registration time
READONLY	2	The value of the corresponding SCF property type is optional, but once given a value it may not be modified
MANDATORY_READONLY	3	The value of the corresponding SCF property type must be provided and subsequently it may not be modified.

### 8.2.1.17 TpServicePropertyName

This data type is identical to TpString and describes a valid SCF property name. The valid SCF property names are listed in the SCF data definition.

### 8.2.1.18 TpServicePropertyName

This data type is identical to TpString. It defines a valid SFC property name. Valid SCF property names are listed in the SCF data definition.

### 8.2.1.19 TpServicePropertyNameList

This data type defines a Numbered Set of Data Elements of type TpServicePropertyName.

### 8.2.1.20 TpServicePropertyValue

This data type is identical to TpString and describes a valid value of a SCF property. The valid SCF property values are given in the SCF data definition.

### 8.2.1.21 TpServicePropertyValueList

This data type defines a Numbered Set of Data Elements of type TpServicePropertyValue

### 8.2.1.22 TpServiceProperty

This data type is a Sequence of Data Elements which describes an “SCF property”. It is a structured data type which consists of:

Sequence Element Name	Sequence Element Type	Documentation
ServicePropertyName	TpServicePropertyName	
ServicePropertyValueList	TpServicePropertyValueList	
ServicePropertyMode	TpServicePropertyMode	

### 8.2.1.23 TpServicePropertyList

This data type defines a Numbered Set of Data Elements of type TpServiceProperty.

### 8.2.1.24 TpServiceTypeDescription

This type is left as a placeholder but is not used in release 99.

This data type is a Sequence\_of\_Data\_Elements which describes an SCF type. It is a structured data type. It consists of:

Sequence Element Name	Sequence Element Type	Documentation
PropertyStructList	TpPropertyStructList	a sequence of property name and property mode tuples associated with the SCF type
ServiceTypeNameList	TpServiceTypeNameList	the names of the super types of the associated SCF type
EnabledOrDisabled	TpBoolean	an indication whether the SCF type is enabled or disabled

### 8.2.1.25 TpServiceTypeName

This data type is identical to TpString [and describes a valid SCF type name](#).

### 8.2.1.26 TpServiceTypeNameList

This data type defines a Numbered Set of Data Elements of type TpServiceTypeName.

## 8.2.2 Trust and Security Management Data Definitions

### 8.2.2.1 TpAccessType

This data type is identical to a TpString. This identifies the type of access interface requested by the client application. If they request P\_ACCESS, then a reference to the IpAccess interface is returned. (Network operators can define their own access interfaces to satisfy client requirements for different types of access. These can be selected using the TpAccessType, but should be preceded by the string "SP\_". The following values are defined for OSA release 99:

String Value	Description
NULL	An empty (NULL) string indicates the default access type
P_ACCESS	Access using the OSA Access Interfaces: IpAccess and IpAppAccess

### 8.2.2.2 TpAuthType

This data type is identical to a TpString. It identifies the type of authentication mechanism requested by the client. It provides Network operators and client's with the opportunity to use an alternative to the OSA Authentication interface, e.g. CORBA Security. OSA Authentication is the default authentication method. Other Network operator specific capabilities may also be used, but should be preceded by the string "SP\_". The following values are defined for OSA release 99:

String Value	Description
NULL	An empty (NULL) string indicates the default authentication method: OSA Authentication.
P_AUTHENTICATION	Authenticate using the OSA Authentication Interfaces: IpAuthentication and IpAppAuthentication

### 8.2.2.3 TpAuthCapability

This data type is identical to a TpString, and is defined as a string of characters that identify the authentication capabilities that could be supported by the OSA. Other Network operator specific capabilities may also be used, but should be preceded by the string "SP\_". Capabilities may be concatenated, using commas (,) as the separation character. The following values are defined for OSA release 99.

String Value	Description
NULL	An empty (NULL) string indicates no client capabilities.
P_DES_56	A simple transfer of secret information that is shared between the client application and the framework with protection against interception on the link provided by the DES algorithm with a 56bit shared secret key
P_RSA_512	A public-key cryptography system providing authentication without prior exchange of secrets using 512 bit keys
P_RSA_1024	A public-key cryptography system providing authentication without prior exchange of secrets using 1024bit keys

### 8.2.2.4 TpAuthCapabilityList

This data type is identical to a TpString. It is a string of multiple TpAuthCapability concatenated using a comma (,) as the separation character.

### 8.2.2.5 TplInterfaceName

This data type is identical to a TpString, and is defined as a string of characters that identify the names of the framework SCFs that are supported by the OSA API. Other Network operator specific SCFs may also be used, but should be preceded by the string "SP\_". The following values are defined for OSA release 99.

Character String Value	Description
NULL	An empty (NULL) string indicates no interface.
P_DISCOVERY	The name for the Discovery interface.
P_OAM	The name for the OA&M interface.
P_TRUST_AND_SECURITY_MANAGEMENT	The name for the Trust and Security Management interface
P_INTEGRITY_MANAGEMENT	The name for the Integrity Management interface.

### 8.2.2.6 TpServiceAccessControl

This is Sequence of Data Elements containing the access control policy information controlling access to the service capability feature, and the trustLevel that the Network operator has assigned to the client application.

Sequence Element Name	Sequence Element Type
Policy	TpString
TrustLevel	TpString

The policy parameter indicates whether access has been granted or denied. If granted then the parameter trustLevel must also have a value.

The trustLevel parameter indicates the trust level that the Network operator has assigned to the client application.

### 8.2.2.7 TpServiceToken

This data type is identical to a TpString, and identifies a selected SCF. This is a free format text token returned by the framework, which can be signed as part of a service agreement. This will contain Network operator specific information relating to the service level agreement. The serviceToken has a limited lifetime, which is the same as the lifetime of the service agreement in normal conditions. If something goes wrong the serviceToken expires, and any method accepting

the serviceToken will return an error code (P\_INVALID\_SERVICE\_TOKEN). Service Tokens will automatically expire if the client or framework invokes the endAccess method on the other's corresponding access interface.

### 8.2.2.8 TpSignatureAndServiceMgr

This is a Sequence of Data Elements containing the digital signature of the framework for the service agreement, and a reference to the SCF manager interface of the SCF.

Sequence Element Name	Sequence Element Type
DigitalSignature	TpStringRef
ServiceMgrInterface	IpServiceRef

The digitalSignature is the signed version of a hash of the service token and agreement text given by the client application.

The ServiceMgrInterface is a reference to the SCF manager interface for the selected SCF.

### 8.2.2.9 TpSigningAlgorithm

This data type is identical to a TpString, and is defined as a string of characters that identify the signing algorithm that must be used. Other Network operator specific capabilities may also be used, but should be preceded by the string "SP\_". The following values are defined for OSA release 99.

String Value	Description
NULL	An empty (NULL) string indicates no signing algorithm is required
P_MD5_RSA_512	MD5 takes an input message of arbitrary length and produces as output a 128-bit message digest of the input. This is then encrypted with the private key under the RSA public-key cryptography system using a 512 bit key.
P_MD5_RSA_1024	MD5 takes an input message of arbitrary length and produces as output a 128-bit message digest of the input. This is then encrypted with the private key under the RSA public-key cryptography system using a 1024 bit key

## 8.2.3 Integrity Management Data Definitions

### 8.2.3.1 TpActivityTestRes

This type is identical to TpString and is an implementation specific result. The values in this data type are "Available" or "Unavailable".

### 8.2.3.2 TpFaultStatsRecord

This defines the set of records to be returned giving fault information for the requested time period.

Sequence Element Name	Sequence Element Type
Period	TpTimeInterval
FaultRecords	TpFaultStatsSet

### 8.2.3.3 TpFaultStatsSet

This defines the sequence of data elements which provide the statistics on a per fault type basis.

Sequence Element Name	Sequence Element Type
Fault	TpInterfaceFault
Occurrences	TpInt32

MaxDuration	TpInt32
TotalDuration	TpInt32
NumberOfClientsAffected	TpInt32

Occurrences is the number of separate instances of this fault during the period. MaxDuration and TotalDuration are the number of seconds duration of the longest fault and the cumulative total during the period. NumberOfClientsAffected is the number of clients informed of the fault by the framework.

#### 8.2.3.4 TpActivityTestId

This data type is identical to a TpInt32, and is used as a token to match activity test requests with their results..

#### 8.2.3.5 TplInterfaceFault

Defines the cause of the interface fault detected.

Name	Value	Description
INTERFACE_FAULT_UNDEFINED	0	Undefined
INTERFACE_FAULT_LOCAL_FAILURE	1	A fault in the local API software or hardware has been detected
INTERFACE_FAULT_GATEWAY_FAILURE	2	A fault in the gateway API software or hardware has been detected
INTERFACE_FAULT_PROTOCOL_ERROR	3	An error in the protocol used on the client-gateway link has been detected

#### 8.2.3.6 TpSvcUnavailReason

Defines the reason why a SCF is unavailable.

Name	Value	Description
SERVICE_UNAVAILABLE_UNDEFINED	0	Undefined
SERVICE_UNAVAILABLE_LOCAL_FAILURE	1	The Local API software or hardware has failed
SERVICE_UNAVAILABLE_GATEWAY_FAILURE	2	The gateway API software or hardware has failed
SERVICE_UNAVAILABLE_OVERLOADED	3	The SCF is fully overloaded
SERVICE_UNAVAILABLE_CLOSED	4	The SCF has closed itself (e.g. to protect from fraud or malicious attack)

#### 8.2.3.7 TpAPIUnavailReason

Defines the reason why the API is unavailable.

Name	Value	Description
API_UNAVAILABLE_UNDEFINED	0	Undefined
API_UNAVAILABLE_LOCAL_FAILURE	1	The Local API software or hardware has failed
API_UNAVAILABLE_GATEWAY_FAILURE	2	The gateway API software or hardware has failed
API_UNAVAILABLE_OVERLOADED	3	The gateway is fully overloaded
API_UNAVAILABLE_CLOSED	4	The gateway has closed itself (e.g. to protect from fraud or malicious attack)
API_UNAVAILABLE_PROTOCOL_FAILURE	5	The protocol used on the client-gateway link has failed

### 8.2.3.8 TpLoadLevel

Defines the Sequence of Data Elements that specify load level values.

Name	Value	Description
LOAD_LEVEL_NORMAL	0	Normal load
LOAD_LEVEL_OVERLOAD	1	Overload
LOAD_LEVEL_SEVERE_OVERLOAD	2	Severe Overload

### 8.2.3.9 TpLoadThreshold

Defines the Sequence of Data Elements that specify the load threshold value. The actual load threshold value is application and SCF dependent, so is their relationship with load level.

Sequence Element Name	Sequence Element Type
LoadThreshold	TpFloat

### 8.2.3.10 TpLoadInitVal

Defines the Sequence of Data Elements that specify the pair of load level and associated load threshold value.

Sequence Element Name	Sequence Element Type
LoadLevel	TpLoadLevel
LoadThreshold	TpLoadThreshold

### 8.2.3.11 TpTimeInterval

Defines the Sequence of Data Elements that specify a time interval.

Sequence Element Name	Sequence Element Type
StartTime	TpDateAndTime
StopTime	TpDateAndTime

### 8.2.3.12 TpLoadPolicy

Defines the load balancing policy.

Sequence Element Name	Sequence Element Type
LoadPolicy	TpString

### 8.2.3.13 TpLoadStatistic

Defines the Sequence of Data Elements that specify the load statistic record at given timestamp.

Sequence Element Name	Sequence Element Type
ServiceID	TpServiceID
LoadValue	TpFloat
LoadLevel	TpLoadLevel
TimeStamp	TpDateAndTime

LoadValue is expressed in percentage.

### 8.2.3.14 TpLoadStatList

Defines a Numbered Set of Data Elements of TpLoadStatistic.

### 8.2.3.15 TpLoadStatusError

Defines the error code for getting the load status.

Name	Value	Description
LOAD_STATUS_ERROR_UNDEFINED	0	Undefined error
LOAD_STATUS_ERROR_UNAVAILABLE	1	Unable to get the load status

### 8.2.3.16 TpLoadStatisticError

Defines the Sequence of Data Elements that specify the error for getting the load status at given timestamp.

Sequence Element Name	Sequence Element Type
ServiceID	TpServiceID
LoadStatusError	TpFloat
TimeStamp	TpDateAndTime

### 8.2.3.17 TpLoadStatisticErrorList

Defines a Numbered Set of Data Elements of TpLoadStatisticsError.

## 8.3 Generic Call Control Data Definitions

The constants and types defined in the following sections are defined in the *org.threegpp.osa.gccs* package.

### 8.3.1 Interface definitions

#### 8.3.1.1 IpAppCall

Defines the address of an IAppCall Interface.

#### 8.3.1.2 IpAppCallRef

Defines a Reference to type IAppCall

#### 8.3.1.3 IpAppCallRefRef

Defines a Reference to type IAppCallRef.

#### 8.3.1.4 IpAppCallControlManager

Defines the address of an IAppCallControlManager Interface.

#### 8.3.1.5 IpAppCallControlManagerRef

Defines a Reference to type IAppCallControlManager.

#### 8.3.1.6 IpCall

Defines the address of an ICall Interface.

### 8.3.1.7 IpCallRef

Defines a Reference to type ICall.

### 8.3.1.8 IpCallRefRef

Defines a Reference to type ICallRef.

### 8.3.1.9 IpCallControlManager

Defines the address of an ICallControlManager Interface.'

### 8.3.1.10 IpCallControlManagerRef

Defines a Reference to type ICallControlManager.

## 8.3.2 Event Notification data definitions

### 8.3.2.1 TpCallEventName

Defines the names of events being notified with a new call request. The following events are supported. The values may be combined by a logical 'OR' function when requesting the notifications. Additional events that can be requested / received during the call process are found in the TpCallReportType data-type.

Name	Value	Description
P_EVENT_NAME_UNDEFINED	0	Undefined
P_EVENT_GCCS_OFFHOOK_EVENT	1	GCCS – Offhook event. This can be used for hot-line features. In case this event is set in the TpCallEventCriteria, only the originating address(es) may be specified in the criteria.
P_EVENT_GCCS_ADDRESS_COLLECTED_EVENT	2	GCCS – Address information collected The network has collected the information from the calling party, but not yet analysed the information. The number can still be incomplete. Applications might set notification for this event when part of the number analysis needs to be done in the application.
P_EVENT_GCCS_ADDRESS_ANALYSED_EVENT	4	GCCS – Address information is analysed. The dialled number is a valid and complete number in the network.
P_EVENT_GCCS_CALLED_PARTY_BUSY	8	GCCS – Called party is busy
P_EVENT_GCCS_CALLED_PARTY_UNREACHABLE	16	GCCS – Called party is unreachable This can happen when the called party has a mobile phone that is switched off.
P_EVENT_GCCS_NO_ANSWER_FROM_CALLED_PARTY	32	GCCS – No answer from called party
P_EVENT_GCCS_ROUTE_SELECT_FAILURE	64	GCCS – Failure in routing the call
P_EVENT_GCCS_ANSWER_FROM_CALL_PARTY	128	GCCS – Party answered call.

### 8.3.2.2 TpCallEventCriteria

Defines the Sequence of Data Elements that specify the criteria for an event notification.

Sequence Element Name	Sequence Element Type	Description
DestinationAddress	TpAddressRange	Defines the destination address or address range for which the notification is requested

OriginationAddress	TpAddressRange	Defines the origination address or address range for which the notification is requested
CallEventName	TpCallEventName	Name of the event(s)
CallNotificationType	TpCallNotificationType	Indicates whether it is related to the originating or the terminating user in the call.
MonitorMode	TpCallMonitorMode	Defines the mode that the call is in following the notification. Monitor mode P_CALL_MONITOR_MODE_DO_NOT_MONITOR is not a legal value here.

### 8.3.2.3 TpCallEventCriteriaResult

Defines a sequence of data elements that specify a requested call event notification criteria with the associated assignmentID.

Sequence Element Name	Sequence Element Type	Sequence Element Description
EventCriteria	TpCallEventCriteria	The event criteria that were specified by the application.
AssignmentID	TpInt32	The associated assignmentID. This can be used to disable the notification.

### 8.3.2.4 TpCallEventCriteriaResultSet

Defines a set of TpCallEventCriteriaResult.

### 8.3.2.5 TpCallNotificationType

Defines the type of notification. Indicates whether it is related to the originating or the terminating user in the call.

Name	Value	Description
P_ORIGINATING	1	Indicates that the notification is related to the originating user in the call.
P_TERMINATING	2	Indicates that the notification is related to the terminating user in the call.

### 8.3.2.6 TpCallEventInfo

Defines the Sequence of Data Elements that specify the information returned to the application in a New Call event notification.

Sequence Element Name	Sequence Element Type
DestinationAddress	TpAddress
OriginatingAddress	TpAddress
OriginalDestinationAddress	TpAddress
RedirectingAddress	TpAddress
CallAppInfo	TpCallAppInfoSet
CallEventName	TpCallEventName
CallNotificationType	TpCallNotificationType

### 8.3.3 Generic Call Control Type definitions

#### 8.3.3.1 TpCallAlertingMechanism

This data type is identical to a TpInt32 , and defines the mechanism that will be used to alert a called party. The values of this data type are operator specific.

#### 8.3.3.2 TpCallAppInfo

Defines the Tagged Choice of Data Elements that specify application-related call information.

	Tag Element Type	
	TpCallAppInfoType	

Tag Element Value	Choice Element Type	Choice Element Name
P_CALL_APP_ALERTING_MECHANISM	TpCallAlertingMechanism	CallAppAlertingMechanism
P_CALL_APP_NETWORK_ACCESS_TYPE	TpCallNetworkAccessType	CallAppNetworkAccessType
P_CALL_APP_TELE_SERVICE	TpCallTeleService	CallAppTeleService
P_CALL_APP_BEARER_SERVICE	TpCallBearerService	CallAppBearerService
P_CALL_APP_PARTY_CATEGORY	TpCallPartyCategory	CallAppPartyCategory
P_CALL_APP_PRESENTATION_ADDRESS	TpAddress	CallAppPresentationAddress
P_CALL_APP_GENERIC_INFO	TpString	CallAppGenericInfo
P_CALL_APP_ADDITIONAL_ADDRESS	TpAddress	CallAppAdditionalAddress

CallAppPresentationAddress contains presentation address.

CallAppGenericInfo contains operator specific information.

CallAppAdditionalAddress contains additional address.

#### 8.3.3.3 TpCallAppInfoType

Defines the type of application related call information.

Name	Value	Description
P_CALL_APP_UNDEFINED	0	Undefined
P_CALL_APP_ALERTING_MECHANISM	1	The alerting mechanism or pattern to use
P_CALL_APP_NETWORK_ACCESS_TYPE	2	The network access type (e.g. ISDN)
P_CALL_APP_TELE_SERVICE	4	Indicates the tele-service (e.g. speech) and related info such as clearing programme
P_CALL_APP_BEARER_SERVICE	5	Indicates the bearer service (e.g. 64kb/s unrestricted data).
P_CALL_APP_PARTY_CATEGORY	6	The category of the calling or called party
P_CALL_APP_PRESENTATION_ADDRESS	7	The address to be presented to other call parties
P_CALL_APP_GENERIC_INFO	8	Carries unspecified application-Service

		Capability Feature information
P_CALL_APP_ADDITIONAL_ADDRESS	9	Indicates an additional address

### 8.3.3.4 TpCallAppInfoSet

Defines a Numbered Set of Data Elements of TpCallAppInfo.

### 8.3.3.5 TpCallBearerService

This data type defines the type of call application-related specific information (Q.931: Information Transfer Capability, and 3G TS 22.002)

Name	Value	Description
P_CALL_BEARER_SERVICE_UNKNOWN	0	Bearer capability information unknown at this time
P_CALL_BEARER_SERVICE_SPEECH	1	Speech
P_CALL_BEARER_SERVICE_DIGITALUNRESTRICTED	2	Unrestricted digital information
P_CALL_BEARER_SERVICE_DIGITALRESTRICTED	3	Restricted digital information
P_CALL_BEARER_SERVICE_AUDIO	4	3.1 kHz audio
P_CALL_BEARER_SERVICE_DIGITALUNRESTRICTEDTONES	5	Unrestricted digital information with tones/announcements
P_CALL_BEARER_SERVICE_VIDEO	6	Video

### 8.3.3.6 TpCallChargePlan

Defines the Sequence of Data Elements that specify the charge plan for the call.

Sequence Element Name	Sequence Element Type	Description
ChargeOrderType	TpCallChargeOrder	Charge order
Currency	TpString	Currency unit according to ISO-4217:1995
AdditionalInfo	TpString	Descriptive string which is sent to the billing system without prior evaluation. Could be included in the ticket.

Valid Currencies are:

ADP, AED, AFA, ALL, AMD, ANG, AON, AOR, ARS, ATS, AUD, AWG, AZM, BAM,  
 BBD, BDT, BEF, BGL, BGN, BHD, BIF, BMD, BND, BOB, BOV, BRL, BSD, BTN,  
 BWP, BYB, BZD, CAD, CDF, CHF, CLF, CLP, CNY, COP, CRC, CUP, CVE, CYP,  
 CZK, DEM, DJF, DKK, DOP, DZD, ECS, ECV, EEK, EGP, ERN, ESP, ETB, EUR,  
 FIM, FJD, FKP, FRF, GBP, GEL, GHC, GIP, GMD, GNF, GRD, GTQ, GWP, GYD,  
 HKD, HNL, HRK, HTG, HUF, IDR, IEP, ILS, INR, IQD, IRR, ISK, ITL, JMD,  
 JOD, JPY, KES, KGS, KHR, KMF, KPW, KRW, KWD, KYD, KZT, LAK, LBP, LKR,  
 LRD, LSL, LTL, LUF, LVL, LYD, MAD, MDL, MGF, MKD, MMK, MNT, MOP, MRO,  
 MTL, MUR, MVR, MWK, MXN, MXV, MYR, MZM, NAD, NGN, NIO, NLG, NOK, NPR,  
 NZD, OMR, PAB, PEN, PGK, PHP, PKR, PLN, PTE, PYG, QAR, ROL, RUB, RUR,

RWF, SAR, SBD, SCR, SDD, SEK, SGD, SHP, SIT, SKK, SLL, SOS, SRG, STD, SVC, SYP, SZL, THB, TJR, TMM, TND, TOP, TPE, TRL, TTD, TWD, TZS, UAH, UGX, USD, USN, USS, UYU, UZS, VEB, VND, VUV, WST, XAF, XAG, XAU, XBA, XBB, XBC, XBD, XCD, XDR, XFO, XFU, XOF, XPD, XPF, XPT, XTS, XXX, YER, YUM, ZAL, ZAR, ZMK, ZRN, ZWD.

XXX is used for transactions where no currency is involved.

### 8.3.3.7 TpCallChargeOrder

Defines the Tagged Choice of Data Elements that specify the charge plan for the call.

	Tag Element Type	
	TpCallChargeOrderCategory	

Tag Element Value	Choice Element Type	Choice Element Name
P_CALL_CHARGE_PER_TIME	TpChargePerTime	ChargePerTime
P_CALL_CHARGE_NETWORK	TpString	NetworkCharge

### 8.3.3.8 TpCallChargeOrderCategory

Name	Value	Description
P_CALL_CHARGE_PER_TIME	0	Charge per time
P_CALL_CHARGE_NETWORK	1	Operator specific charge plan specification, e.g. charging table name / charging table entry

### 8.3.3.9 TpCallEndedReport

Defines the Sequence of Data Elements that specify the reason for the call ending.

Sequence Element Name	Sequence Element Type	
CallLegSessionID	TpSessionID	The leg that initiated the release of the call.  If the call release was not initiated by the leg, then this value is set to -1.
Cause	TpCallReleaseCause	The cause of the call ending.

### 8.3.3.10 TpCallError

Defines the Sequence of Data Elements that specify the additional information relating to an undefined call error.

Sequence Element Name	Sequence Element Type
ErrorTime	TpDateAndTime
ErrorType	TpCallErrorType
AdditionalErrorInfo	TpCallAdditionalErrorInfo

### 8.3.3.11 TpCallAdditionalErrorInfo

Defines the Tagged Choice of Data Elements that specify additional call error and call error specific information. This is also used to specify call leg errors and call information errors.

	Tag Element Type	
	TpCallErrorType	

Tag Element Value	Choice Element Type	Choice Element Name
P_CALL_ERROR_UNDEFINED	NULL	Undefined
P_CALL_ERROR_INVALID_ADDRESS	TpAddressError	CallErrorInvalidAddress
P_CALL_ERROR_INVALID_STATE	NULL	Undefined

### 8.3.3.12 TpCallErrorType

Defines a specific call error.

Name	Value	Description
P_CALL_ERROR_UNDEFINED	0	Undefined; the method failed or was refused, but no specific reason can be given.
P_CALL_ERROR_INVALID_ADDRESS	1	The operation failed because an invalid address was given
P_CALL_ERROR_INVALID_STATE	2	The call was not in a valid state for the requested operation

### 8.3.3.13 TpCallFault

Defines the cause of the call fault detected.

Name	Value	Description
P_CALL_FAULT_UNDEFINED	0	Undefined
P_TIMEOUT_ON_RELEASE	1	This fault occurs when the final report has been sent to the application, but the application did not explicitly release or deassign the call object, within a specified time. The timer value is operator specific.
P_TIMEOUT_ON_INTERRUPT	2	This fault occurs when the application did not instruct the gateway how to handle the call within a specified time, after the gateway reported an event that was requested by the application in interrupt mode. The timer value is operator specific.

### 8.3.3.14 TpCallIdentifier

Defines the Sequence of Data Elements that unambiguously specify the Generic Call object

Sequence Element Name	Sequence Element Type	Sequence Element Description
CallReference	IpCallRef	This element specifies the interface reference for the call object.
CallSessionID	TpSessionID	This element specifies the call session ID of the call.

### 8.3.3.15 TpCallIdentifierRef

Defines a Reference to type TpCallIdentifier.

### 8.3.3.16 TpCallInfoReport

Defines the Sequence of Data Elements that specify the call information requested. Information that was not requested is invalid.

Sequence Element Name	Sequence Element Type	Description
CallInfoType	TpCallInfoType	The type of call report.
CallInitiationStartTime	TpDateAndTime	The time and date when the call, or follow-on call, was started.
CallConnectedToResourceTime	TpDateAndTime	The date and time when the call was connected to the resource. This data element is only valid where information on user interaction is reported.
CallConnectedToDestinationTime	TpDateAndTime	The date and time when the call was connected to the destination (i.e. when the destination answered the call). If the destination did not answer the time is set to an empty string. This data element is invalid where information on user interaction is reported with an intermediate report.
CallEndTime	TpDateAndTime	The date and time when the call, follow-on call or user-interaction was terminated.
Cause	TpCallReleaseCause	The cause of call termination.

### 8.3.3.17 TpCallInfoType

Defines the type of call information requested and reported. The values may be combined by a logical 'OR' function.

Name	Value	Description
P_CALL_INFO_UNDEFINED	00h	Undefined
P_CALL_INFO_TIMES	01h	Relevant call times
P_CALL_INFO_RELEASE_CAUSE	02h	Call release cause
P_CALL_INFO_INTERMEDIATE	04h	Send only intermediate reports. When this is not specified the information report will only be sent when the call has ended. When intermediate reports are requested a report will be generated between follow-on calls, i.e. when a party leaves the call.

### 8.3.3.18 TpCallMonitorMode

Defines the mode that the call will monitor for events, or the mode that the call is in following a detected event.

Name	Value	Description
P_CALL_MONITOR_MODE_INTERRUPT	0	The call event is intercepted by the call control SCF and call processing is interrupted. The application is notified of the event and call processing resumes following an appropriate API call or network event (such as a call release)
P_CALL_MONITOR_MODE_NOTIFY	1	The call event is detected by the call control SCF but not intercepted. The application is notified of the event and call processing continues
P_CALL_MONITOR_MODE_DO_NOT_MONITOR	2	Do not monitor for the event

### 8.3.3.19 TpCallNetworkAccessType

This data defines the bearer capabilities associated with the call. (3G TS 24.002) This information is network operator specific and may not always be available because there is no standard protocol to retrieve the information.

Name	Value	Description
P_CALL_NETWORK_ACCESS_TYPE_UNKNOWN	0	Network type information unknown at this time
P_CALL_NETWORK_ACCESS_TYPE_POT	1	POTS
P_CALL_NETWORK_ACCESS_TYPE_ISDN	2	ISDN
P_CALL_NETWORK_ACCESS_TYPE_DIALUPINTERNET	3	Dial-up Internet
P_CALL_NETWORK_ACCESS_TYPE_XDSL	4	xDSL
P_CALL_NETWORK_ACCESS_TYPE_WIRELESS	5	Wireless

### 8.3.3.20 TpCallOverloadType

Defines the type of call overload that has been detected (and possibly acted upon) by the network.

Name	Value	Description
P_CALL_OVERLOAD_TYPE_UNDEFINED	0	Infinite interval (do not admit any calls)

P_CALL_OVERLOAD_TYPE_NEW_CALLS	1	New calls to the application are causing overload (i.e. inbound overload)
P_CALL_OVERLOAD_TYPE_ROUTED_CALLS	2	Calls being routed to destination or origination addresses by the application are causing overload (i.e. outbound overload)

### 8.3.3.21 TpCallServiceCode

Defines the Sequence of Data Elements that specify the service code and type of service code received during a call. The service code type defines how the value string should be interpreted.

Sequence Element Name	Sequence Element Type
CallServiceCodeType	TpCallServiceCodeType
ServiceCodeValue	TpString

### 8.3.3.22 TpCallServiceCodeType

Defines the different types of service codes that can be received during the call.

Name	Value	Description
P_CALL_SERVICE_CODE_UNDEFINED	0	The type of service code is unknown. The corresponding string is operator specific.
P_CALL_SERVICE_CODE_DIGITS	1	The user entered a digit sequence during the call. The corresponding string is an ascii representation of the received digits.
P_CALL_SERVICE_CODE_FACILITY	2	A facility information element is received. The corresponding string contains the facility information element as defined in ITU Q.932
P_CALL_SERVICE_CODE_U2U	3	A user-to-user message was received. The associated string contains the content of the user-to-user information element.
P_CALL_SERVICE_CODE_HOOKFLASH	4	The user performed a hookflash, optionally followed by some digits. The corresponding string is an ascii representation of the entered digits.
P_CALL_SERVICE_CODE_RECALL	5	The user pressed the register recall button, optionally followed by some digits. The corresponding string is an ascii representation of the entered digits.

### 8.3.3.23 TpCallPartyCategory

This data type defines the category of a calling party. (Q.763: Calling Party Category / Called Party Category)

Name	Value	Description
P_CALL_PARTY_CATEGORY_UNKNOWN	0	calling party's category unknown at this time
P_CALL_PARTY_CATEGORY_OPERATOR_F	1	operator, language French
P_CALL_PARTY_CATEGORY_OPERATOR_E	2	operator, language English
P_CALL_PARTY_CATEGORY_OPERATOR_G	3	operator, language German
P_CALL_PARTY_CATEGORY_OPERATOR_R	4	operator, language Russian
P_CALL_PARTY_CATEGORY_OPERATOR_S	5	operator, language Spanish

P_CALL_PARTY_CATEGORY_ORDINARY_SUB	6	ordinary calling subscriber
P_CALL_PARTY_CATEGORY_PRIORITY_SUB	7	calling subscriber with priority
P_CALL_PARTY_CATEGORY_DATA_CALL	8	data call (voice band data)
P_CALL_PARTY_CATEGORY_TEST_CALL	9	test call
P_CALL_PARTY_CATEGORY_PAYPHONE	10	payphone

### 8.3.3.24 TpCallReleaseCause

Defines the Sequence of Data Elements that specify the cause of the release of a call.

Sequence Element Name	Sequence Element Type
Value	TpInt32
Location	TpInt32

Note: the Value and Location are specified as in ITU-T recommendation Q.850.

### 8.3.3.25 TpCallReport

Defines the Sequence of Data Elements that specify the call report and call leg report specific information.

Sequence Element Name	Sequence Element Type
MonitorMode	TpCallMonitorMode
CallEventTime	TpDateAndTime
CallReportType	TpCallReportType
AdditionalReportInfo	TpCallAdditionalReportInfo

### 8.3.3.26 TpCallAdditionalReportInfo

Defines the Tagged Choice of Data Elements that specify additional call report information for certain types of reports.

	Tag Element Type	
	TpCallReportType	

Tag Element Value	Choice Element Type	Choice Element Name
P_CALL_REPORT_UNDEFINED	NULL	Undefined
P_CALL_REPORT_PROGRESS	NULL	Undefined
P_CALL_REPORT_ALERTING	NULL	Undefined
P_CALL_REPORT_ANSWER	NULL	Undefined
P_CALL_REPORT_REFUSED_BUSY	TpCallReleaseCause	RefusedBusy
P_CALL_REPORT_NO_ANSWER	NULL	Undefined
P_CALL_REPORT_DISCONNECT	TpCallReleaseCause	CallDisconnect
P_CALL_REPORT_REDIRECTED	TpAddress	ForwardAddress
P_CALL_REPORT_SERVICE_CODE	TpCallServiceCode	ServiceCode
P_CALL_REPORT_ROUTING_FAILURE	TpCallReleaseCause	RoutingFailure

### 8.3.3.27 TpCallReportRequest

Defines the Sequence of Data Elements that specify the criteria relating to call report requests.

Sequence Element Name	Sequence Element Type
MonitorMode	TpCallMonitorMode
CallReportType	TpCallReportType
AdditionalReportCriteria	TpCallAdditionalReportCriteria

### 8.3.3.28 TpCallAdditionalReportCriteria

Defines the Tagged Choice of Data Elements that specify specific criteria.

	Tag Element Type	
	TpCallReportType	

Tag Element Value	Choice Element Type	Choice Element Name
P_CALL_REPORT_UNDEFINED	NULL	Undefined
P_CALL_REPORT_PROGRESS	NULL	Undefined
P_CALL_REPORT_ALERTING	NULL	Undefined
P_CALL_REPORT_ANSWER	NULL	Undefined
P_CALL_REPORT_BUSY	NULL	Undefined
P_CALL_REPORT_NO_ANSWER	TpDuration	NoAnswerDuration
P_CALL_REPORT_DISCONNECT	NULL	Undefined
P_CALL_REPORT_REDIRECTED	NULL	Undefined
P_CALL_REPORT_SERVICE_CODE	TpCallServiceCode	ServiceCode
P_CALL_REPORT_ROUTING_FAILURE	NULL	Undefined

### 8.3.3.29 TpCallReportRequestSet

Defines a Numbered Set of Data Elements of TpCallReportRequest.

### 8.3.3.30 TpCallReportType

Defines a specific call event report type.

Name	Value	Description
P_CALL_REPORT_UNDEFINED	0	Undefined
P_CALL_REPORT_PROGRESS	1	Call routing progress event: an indication from the network that progress has been made in routing the call to the requested called party.
P_CALL_REPORT_ALERTING	2	Call is alerting at the called party.
P_CALL_REPORT_ANSWER	3	Call answered at address
P_CALL_REPORT_BUSY	4	Called address refused call due to busy
P_CALL_REPORT_NO_ANSWER	5	No answer at called address
P_CALL_REPORT_DISCONNECT	6	The called party has disconnected.
P_CALL_REPORT_REDIRECTED	7	Call redirected to new address: an indication from the network that the call has been

		redirected to a new address.
P_CALL_REPORT_SERVICE_CODE	8	Mid-call service code received
P_CALL_REPORT_ROUTING_FAILURE	9	Call routing failed - re-routing is possible

### 8.3.3.31 TpCallServiceCode

Defines the service code received during a call. For example, this may be a digit sequence, user-user information, recall, flash-hook or ISDN Facility Information Element.

This data type is identical to a TpString. The coding of this data type is operator specific. However, the values defined in ISUP ITU Recommendation Q.763 are suggested for this data type.

### 8.3.3.32 TpCallTeleService

This data type defines the tele-service associated with the call. (Q.763: User Teleservice Information, Q.931: High Layer Compatibility Information, and 3G TS 22.003)

Name	Value	Description
P_CALL_TELE_SERVICE_UNKNOWN	0	Teleservice information unknown at this time
P_CALL_TELE_SERVICE_TELEPHONY	1	Telephony
P_CALL_TELE_SERVICE_FAX_2_3	2	Facsimile Group 2/3
P_CALL_TELE_SERVICE_FAX_4_I	3	Facsimile Group 4, Class I
P_CALL_TELE_SERVICE_FAX_4_II_III	4	Facsimile Group 4, Classes II and III
P_CALL_TELE_SERVICE_VIDEOTEX_SYN	5	Syntax based Videotex
P_CALL_TELE_SERVICE_VIDEOTEX_INT	6	International Videotex interworking via gateways or interworking units
P_CALL_TELE_SERVICE_TELEX	7	Telex service
P_CALL_TELE_SERVICE_MHS	8	Message Handling Systems
P_CALL_TELE_SERVICE_OSI	9	OSI application
P_CALL_TELE_SERVICE_FTAM	10	FTAM application
P_CALL_TELE_SERVICE_VIDEO	11	Videotelephony
P_CALL_TELE_SERVICE_VIDEO_CONF	12	Videoconferencing
P_CALL_TELE_SERVICE_AUDIOGRAPH_CONF	13	Audiographic conferencing
P_CALL_TELE_SERVICE_MULTIMEDIA	14	Multimedia services
P_CALL_TELE_SERVICE_CS_INI_H221	15	Capability set of initial channel of H.221
P_CALL_TELE_SERVICE_CS_SUB_H221	16	Capability set of subsequent channel of H.221
P_CALL_TELE_SERVICE_CS_INI_CALL	17	Capability set of initial channel associated with an active 3.1 kHz audio or speech call.
P_CALL_TELE_SERVICE_DATATRAFFIC	18	Data traffic.
P_CALL_TELE_SERVICE_EMERGENCY_CALLS	19	Emergency Calls
P_CALL_TELE_SERVICE_SMS_MT_PP	20	Short message MT/PP
P_CALL_TELE_SERVICE_SMS_MO_PP	21	Short message MO/PP
P_CALL_TELE_SERVICE_CELL_BROADCAST	22	Cell Broadcast Service
P_CALL_TELE_SERVICE_ALT_SPEECH_FAX_3	23	Alternate speech and facsimile group 3
P_CALL_TELE_SERVICE_AUTOMATIC_FAX_3	24	Automatic Facsimile group 3
P_CALL_TELE_SERVICE_VOICE_GROUP_CALL	25	Voice Group Call Service
P_CALL_TELE_SERVICE_VOICE_BROADCAST	26	Voice Broadcast Service

### 8.3.3.33 TpCallSuperviseReport

Defines the responses from the call control SCF for calls that are supervised. The values may be combined by a logical 'OR' function.

Name	Value	Description
P_CALL_SUPERVISE_TIMEOUT	01h	The call supervision timer has expired
P_CALL_SUPERVISE_CALL_ENDED	02h	The call has ended, either due to timer expiry or call party release. In case the called party disconnects but a follow-on call can still be made also this indication is used.
P_CALL_SUPERVISE_TONE_APPLIED	04h	A warning tone has been applied. This is only sent in combination with P_CALL_SUPERVISE_TIMEOUT.
P_CALL_SUPERVISE_UI_FINISHED	08h	The user interaction has finished.

### 8.3.3.34 TpCallSuperviseTreatment

Defines the treatment of the call by the call control SCF when the call supervision timer expires. The values may be combined by a logical 'OR' function.

Name	Value	Description
P_CALL_SUPERVISE_RELEASE	01h	Release the call when the call supervision timer expires
P_CALL_SUPERVISE_RESPOND	02h	Notify the application when the call supervision timer expires
P_CALL_SUPERVISE_APPLY_TONE	04h	Send a warning tone to the controlling party when the call supervision timer expires. If call release is requested, then the call will be released following the tone after an administered time period.

## 8.4 User Interaction Data Definitions

The constants and types defined in the following sections are defined in the *org.threegpp.osa.guis* package.

### 8.4.1 Interface definitions

#### 8.4.1.1 IpUI

Defines the address of an IUI Interface.

#### 8.4.1.2 IpUIRef

Defines a Reference to type IUI.

#### 8.4.1.3 IpUIRefRef

Defines a Reference to type IUIRef.

#### 8.4.1.4 IpUIManager

Defines the address of an IUIManager Interface.

#### 8.4.1.5 IpUIManagerRef

Defines a Reference to type IUIManager.

#### 8.4.1.6 IpAppUI

Defines the address of an IAppUI Interface.

#### 8.4.1.7 IpAppUIRef

Defines a Reference to type IAppUI.

#### 8.4.1.8 IpAppUIRefRef

Defines a Reference to type IAppUIRef.

#### 8.4.1.9 IpAppUIManager

Defines the address of an IAppUIManager Interface.

#### 8.4.1.10 IpAppUIManagerRef

Defines a Reference to type IAppUIManager.

### 8.4.2 Type definitions

#### 8.4.2.1 TpUICallIdentifier

Defines the Sequence of Data Elements that unambiguously specify the UICall object

Structure Element Name	Structure Element Type	Structure Element Description
UICallRef	IpUICallRef	This element specifies the interface reference for the UICall object.
UserInteractionSessionID	TpSessionID	This element specifies the user interaction session ID.

#### 8.4.2.2 TpUICallIdentifierRef

Defines a reference to type TpUICallIdentifier.

#### 8.4.2.3 TpUICollectCriteria

Defines the Sequence of Data Elements that specify the additional properties for the collection of information, such as the end character, first character timeout, inter-character timeout, and maximum interaction time.

Structure Element Name	Structure Element Type
MinLength	TpInt32
MaxLength	TpInt32
EndSequence	TpString
StartTimeout	TpDuration
InterCharTimeout	TpDuration

The structure elements specify the following criteria:

MinLength: Defines the minimum number of characters (e.g. digits) to collect.

MaxLength: Defines the maximum number of characters (e.g. digits) to collect.

EndSequence: Defines the character or characters which terminate an input of variable length, e.g. phonenumbers.

StartTimeout: specifies the value for the first character time-out timer. The timer is started when the announcement has been completed or has been interrupted. The user should enter the start of the response (e.g. first digit) before the timer expires. If the start of the response is not entered before the timer expires, the input is regarded to be erroneous. After receipt of the start of the response, which may be valid or invalid, the timer is stopped.

InterCharTimeOut: specifies the value for the inter-character time-out timer. The timer is started when a response (e.g. digit) is received, and is reset and restarted when a subsequent response is received. The responses may be valid or invalid. the announcement has been completed or has been interrupted.

Input is considered successful if the following applies:

If the `EndSequence` is not present (i.e. NULL):

- when the `InterCharTimeOut` timer expires; or
- when the number of valid digits received equals the `MaxLength`.

If the `EndSequence` is present:

- when the `InterCharTimeOut` timer expires; or
- when the `EndSequence` is received; or
- when the number of valid digits received equals the `MaxLength`.

In the case the number of valid characters received is less than the `MinLength` when the `InterCharTimeOut` timer expires or when the `EndSequence` is received, the input is considered erroneous.

The collected characters (including the `EndSequence`) are sent to the client application when input has been successful.

#### 8.4.2.4 TpUIError

Defines the UI call error codes.

Name	Value	Description
P_UI_ERROR_UNDEFINED	0	Undefined error
P_UI_ERROR_ILLEGAL_ID	1	The information id specified is invalid
P_UI_ERROR_ID_NOT_FOUND	2	A legal information id is not known to the User Interaction SCF
P_UI_ERROR_RESOURCE_UNAVAILABLE	3	The information resources used by the User Interaction SCF are unavailable, e.g. due to an overload situation.
P_UI_ERROR_ILLEGAL_RANGE	4	The values for minimum and maximum collection length are out of range
P_UI_ERROR_IMPROPER_CALLER_RESPONSE	5	Improper user response
P_UI_ERROR_ABANDON	6	The specified leg is disconnected before the send information completed
P_UI_ERROR_NO_OPERATION_ACTIVE	7	There is no active user interaction for the specified leg. Either the application did not start any user interaction or the user interaction was already finished when the <code>abortAction_Req()</code> was called.
P_UI_ERROR_NO_SPACE_AVAILABLE	8	There is no more storage capacity to record the message when the <code>recordMessage()</code> operation was called

The call user interaction object will be automatically de-assigned if the error `P_UI_ERROR_ABANDON` is reported, as a corresponding call or call leg object no longer exists.

#### 8.4.2.5 TpUIEventCriteria

Defines the Sequence of Data Elements that specify the additional criteria for receiving a UI notification

Structure Element Name	Structure Element Type	Description
OriginatingAddress	TpAddressRange	Defines the originating address for which the notification is requested.
DestinationAddress	TpAddressRange	Defines the destination address or address range for which the notification is requested.
ServiceCode	TpString	Defines a 2 digit code indicating the UI to be triggered. The value is operator specific.

#### 8.4.2.6 TpUIEventInfo

Defines the Sequence of Data Elements that specify a UI notification

Structure Element Name	Structure Element Type	
OriginatingAddress	TpAddress	Defines the originating address.
DestinationAddress	TpAddress	Defines the destination address.
ServiceCode	TpString	Defines a 2 digit code indicating the UI to be triggered. The value is operator specific.
DataTypeIndication	TpUIEventInfoDataType	Identifies the type of contents in the dataString.
DataString	TpString	Freely defined data string with a limited length e.g. 160 bytes according to the network policy.

#### 8.4.2.7 TpUIEventInfoDataType

Defines the type of the dataString parameter in the method userInteractionEventNotify.

Name	Value	Description
P_UI_EVENT_DATA_TYPE_UNDEFINED	0	Undefined (e.g. binary data)
P_UI_EVENT_DATA_TYPE_UNSPECIFIED	1	Unspecified data
P_UI_EVENT_DATA_TYPE_TEXT	2	Text
P_UI_EVENT_DATA_TYPE_USSD_DATA	3	USSD data starting with coding scheme

#### 8.4.2.8 TpUIFault

Defines the cause of the UI fault detected.

Name	Value	Description
P_UI_FAULT_UNDEFINED	0	Undefined
P_UI_CALL_DEASSIGNED	1	The related Call object has been deassigned. No further interaction is possible. Already requested announcements will continue but no requested reports will be send to the application.

#### 8.4.2.9 TpUIIdentifier

Defines the Sequence of Data Elements that unambiguously specify the UI object

Structure Element Name	Structure Element Type	Structure Element Description
UIRef	IpUIRef	This element specifies the interface reference for the UI object.
UserInteractionSessionID	TpSessionID	This element specifies the user interaction session ID.

#### 8.4.2.10 TpUIIdentifierRef

Defines a reference to type TpUIIdentifier.

#### 8.4.2.11 TpUIInfo

Defines the Tagged Choice of Data Elements that specify the information to send to the user.

	Tag Element Type	
	TpUIInfoType	

Tag Element Value	Choice Element Type	Choice Element Name
P_UI_INFO_ID	TpInt32	InfoId
P_UI_INFO_DATA	TpString	InfoData
P_UI_INFO_ADDRESS	TpURL	InfoAddress

The choice elements represents the following:

- InfoId: defines the ID of the user information script or stream to send to an end-user. The values of this data type are operator specific.
- InfoData: defines the data to be sent to an end-user's terminal. The data is free-format and the encoding is depending on the resources being used..
- InfoAddress: defines the URL of the text or stream to be sent to an end-user's terminal.

#### 8.4.2.12 TpUIInfoType

Defines the type of the information to be sent to the user.

Name	Value	Description
P_UI_INFO_ID	1	The information to be send to an end-user consists of an ID
P_UI_INFO_DATA	2	The information to be send to an end-user consists of a data string
P_UI_INFO_ADDRESS	3	The information to be send to an end-user consists of a URL.

#### 8.4.2.13 TpUIMessageCriteria

Defines the Sequence of Data Elements that specify the additional properties for the recording of a message

Structure Element Name	Structure Element Type
EndSequence	TpString
MaxMessageTime	TpDuration
MaxMessageSize	TpInt32

The structure elements specify the following criteria:

- EndSequence : Defines the character or characters which terminate an input of variable length, e.g. phonenumbers.
- MaxMessageTime : specifies the maximum duration in seconds of the message that is to be recorded.
- MaxMessageSize : If this parameter is non-zero, it specifies the maximum size in bytes of the message that is to be recorded.

#### 8.4.2.14 TpUIReport

Defines the UI call reports if a response was requested.

Name	Value	Description
P_UI_REPORT_UNDEFINED	0	Undefined report
P_UI_REPORT_ANNOUNCEMENT_ENDED	1	Confirmation that the announcement has ended
P_UI_REPORT_LEGAL_INPUT	2	Information collected., meeting the specified criteria.
P_UI_REPORT_NO_INPUT	3	No information collected. The user immediately entered the delimiter character. No valid information has been returned
P_UI_REPORT_TIMEOUT	4	No information collected. The user did not input any response before the input timeout expired
P_UI_REPORT_MESSAGE_STORED	5	A message has been stored successfully
P_UI_REPORT_MESSAGE_NOT_STORED	6	The message has not been stored successfully

#### 8.4.2.15 TpUIResponseRequest

Defines the situations for which a response is expected following the user interaction.

Name	Value	Description
P_UI_RESPONSE_REQUIRED	1	The User Interaction Call must send a response when the request has completed.
P_UI_LAST_ANNOUNCEMENT_IN_A_ROW	2	This is the final announcement within a sequence. It might, however, be that additional announcements will be requested at a later moment. The Call User Interaction Call SCF may release any used resources in the network. The UI object will not be released.
P_UI_FINAL_REQUEST	4	This is the final request. The UI object will be released after the information has been presented to the user.

This parameter represent a bitmask, i.e. the values can be added to derived the final meaning.

#### 8.4.2.16 TpUIVariableInfo

Defines the Tagged Choice of Data Elements that specify the variable parts in the information to send to the user.

	Tag Element Type	
	TpUIVariablePartType	

Tag Element Value	Choice Element Type	Choice Element Name
P_UI_VARIABLE_PART_INT	TpInt32	VariablePartInteger
P_UI_VARIABLE_PART_ADDRESS	TpString	VariablePartAddress
P_UI_VARIABLE_PART_TIME	TpTime	VariablePartTime
P_UI_VARIABLE_PART_DATE	TpDate	VariablePartDate
P_UI_VARIABLE_PART_PRICE	TpPrice	VariablePartPrice

#### 8.4.2.17 TpUIVariableInfoSet

Defines a Numbered Set of Data Elements of TpUIVariableInfo.

#### 8.4.2.18 TpUIVariablePartType

Defines the type of the variable parts in the information to send to the user.

Name	Value	Description
P_UI_VARIABLE_PART_INT	0	Variable part is of type integer
P_UI_VARIABLE_PART_ADDRESS	1	Variable part is of type address
P_UI_VARIABLE_PART_TIME	2	Variable part is of type time
P_UI_VARIABLE_PART_DATE	3	Variable part is of type date
P_UI_VARIABLE_PART_PRICE	4	Variable part is of type price

## 8.5 Data Session Control Data Definitions

The constants and types defined in the following sections are defined in the *org.threegpp.osa.dscc* package.

## 8.5.1 Interface definitions

### 8.5.1.1 **IpAppDataSession**

Defines the address of an `IpAppDataSession` Interface.

### 8.5.1.2 **IpAppDataSessionRef**

Defines a Reference to type `IpAppDataSession`

### 8.5.1.3 **IpAppDataSessionRefRef**

Defines a Reference to type `IpAppDataSessionRef`.

### 8.5.1.4 **IpAppDataSessionControlManager**

Defines the address of an `IpAppDataSessionControlManager` Interface.

### 8.5.1.5 **IpAppDataSessionControlManagerRef**

Defines a Reference to type `IpAppDataSessionControlManager`.

### 8.5.1.6 **IpDataSession**

Defines the address of an `IpDataSession` Interface.

### 8.5.1.7 **IpDataSessionRef**

Defines a Reference to type `IpDataSession`.

### 8.5.1.8 **IpDataSessionRefRef**

Defines a Reference to type `IpDataSessionRef`.

### 8.5.1.9 **IpDataSessionControlManager**

Defines the address of an `IpDataSessionManager` Interface.

### 8.5.1.10 **IpDataSessionManagerRef**

Defines a Reference to type `IpDataSessionControlManager`.

## 8.5.2 Event Notification data definitions

### 8.5.2.1 **TpDataSessionEventName**

Defines the names of events being notified with a new call request. The following events are supported. The values may be combined by a logical 'OR' function when requesting the notifications. Additional events that can be requested / received during the call process are found in the `TpDataSessionReportType` data-type.

Name	Value	Description
P_EVENT_NAME_UNDEFINED	0	Undefined
P_EVENT_DSCS_SETUP	1	The data session is going to be setup.
P_EVENT_DSCS_ESTABLISHED	2	The data session is established by the network.

### 8.5.2.2 TpDataSessionMonitorMode

Defines the mode that the call will monitor for events, or the mode that the call is in following a detected event.

Name	Value	Description
P_DATA_SESSION_MONITOR_MODE_INTERRUPT	0	The data session event is intercepted by the data session control service and data session establishment is interrupted. The application is notified of the event and data session establishment resumes following an appropriate API call or network event (such as a data session release)
P_DATA_SESSION_MONITOR_MODE_NOTIFY	1	The data session event is detected by the data session control service but not intercepted. The application is notified of the event and data session establishment continues
P_DATA_SESSION_MONITOR_MODE_DO_NOT_MONITOR	2	Do not monitor for the event

### 8.5.2.3 TpDataSessionEventCriteria

Defines the Sequence of Data Elements that specify the criteria for a event notification.

Of the addresses only the Plan and the AddrString are used for the purpose of matching the notifications against the criteria.

Sequence Element Name	Sequence Element Type	Description
DestinationAddress	TpAddressRange	Defines the destination address or address range for which the notification is requested.
OriginatingAddress	TpAddressRange	Defines the origination address or a address range for which the notification is requested.
DataSessionEventName	TpDataSessionEventName	Name of the event(s)
MonitorMode	TpDataSessionMonitorMode	Defines the mode that the Data Session is in following the notification. Monitor mode P_DATA_SESSION_MONITOR_MODE_DO_NOT_MONITOR is not a legal value here.

### 8.5.2.4 TpDataSessionEventInfo

Defines the Sequence of Data Elements that specify the information returned to the application in a Data Session event notification.

Sequence Element Name	Sequence Element Type
DestinationAddress	TpAddress
OriginatingAddress	TpAddress
DataSessionEventName	TpDataSessionEventName
MonitorMode	TpDataSessionMonitorMode

### 8.5.2.5 TpDataSessionChargePlan

Defines the Sequence of Data Elements that specify the charge plan for the call.

Sequence Element Name	Sequence Element Type	Description

ChargeOrderType	TpDataSessionChargeOrder	Charge order
Currency	TpString	Currency unit according to ISO-4217:1995
AdditionalInfo	TpString	Descriptive string which is sent to the billing system without prior evaluation. Could be included in the ticket.

Valid Currencies are:

ADP, AED, AFA, ALL, AMD, ANG, AON, AOR, ARS, ATS, AUD, AWG, AZM, BAM, BBD, BDT, BEF, BGL, BGN, BHD, BIF, BMD, BND, BOB, BOV, BRL, BSD, BTN, BWP, BYB, BZD, CAD, CDF, CHF, CLF, CLP, CNY, COP, CRC, CUP, CVE, CYP, CZK, DEM, DJF, DKK, DOP, DZD, ECS, ECV, EEK, EGP, ERN, ESP, ETB, EUR, FIM, FJD, FKP, FRF, GBP, GEL, GHC, GIP, GMD, GNF, GRD, GTQ, GWP, GYD, HKD, HNL, HRK, HTG, HUF, IDR, IEP, ILS, INR, IQD, IRR, ISK, ITL, JMD, JOD, JPY, KES, KGS, KHR, KMF, KPW, KRW, KWD, KYD, KZT, LAK, LBP, LKR, LRD, LSL, LTL, LUF, LVL, LYD, MAD, MDL, MGF, MKD, MMK, MNT, MOP, MRO, MTL, MUR, MVR, MWK, MXN, MXV, MYR, MZM, NAD, NGN, NIO, NLG, NOK, NPR, NZD, OMR, PAB, PEN, PGK, PHP, PKR, PLN, PTE, PYG, QAR, ROL, RUB, RUR, RWF, SAR, SBD, SCR, SDD, SEK, SGD, SHP, SIT, SKK, SLL, SOS, SRG, STD, SVC, SYP, SZL, THB, TJR, TMM, TND, TOP, TPE, TRL, TTD, TWD, TZS, UAH, UGX, USD, USN, USS, UYU, UZS, VEB, VND, VUV, WST, XAF, XAG, XAU, XBA, XBB, XBC, XBD, XCD, XDR, XFO, XFU, XOF, XPD, XPF, XPT, XTS, XXX, YER, YUM, ZAL, ZAR, ZMK, ZRN, ZWD.

XXX is used for transactions where no currency is involved.

#### 8.5.2.6 TpDataSessionChargeOrder

Defines the Tagged Choice of Data Elements that specify the charge plan for the call.

Tag Element Type	
	TpDataSessionChargeOrderCategory

Tag Element Value	Choice Element Type	Choice Element Name
P_DATA_SESSION_CHARGE_PER_VOLUME	TpChargePerVolume	ChargePerVolume
P_DATA_SESSION_CHARGE_NETWORK	TpString	NetworkCharge

#### 8.5.2.7 TpDataSessionChargeOrderCategory

Name	Value	Description
P_DATA_SESSION_CHARGE_PER_VOLUME	0	Charge per volume
P_DATA_SESSION_CHARGE_NETWORK	1	Operator specific charge plan specification, e.g. charging table name / charging table entry

### 8.5.2.8 TpChargePerVolume

Defines the Sequence of Data Elements that specify the time based charging information. The volume is the sum of uplink and downlink transfer data volumes.

Sequence Element Name	Sequence Element Type	Description
InitialCharge	TpInt32	Initial charge amount (in currency units * 0.0001)
CurrentChargePerKilobyte	TpInt32	Current tariff (in currency units * 0.0001)
NextChargePerKilobyte	TpInt32	Next tariff (in currency units * 0.0001) after tariff switch. Only used in setAdviceOfCharge()

### 8.5.2.9 TpDataSessionIdentifier

Defines the Sequence of Data Elements that unambiguously specify the Data Session object

Sequence Element Name	Sequence Element Type	Sequence Element Description
DataSessionReference	IpDataSessionRef	This element specifies the interface reference for the Data Session object.
DataSessionSessionID	TpSessionID	This element specifies the data session ID of the Data Session.

### 8.5.2.10 TpDataSessionError

Defines the Sequence of Data Elements that specify the additional information relating to acall error.

Sequence Element Name	Sequence Element Type
ErrorTime	TpDateAndTime
ErrorType	TpDataSessionErrorType
AdditionalErrorInfo	TpDataSessionAdditionalErrorInfo

### 8.5.2.11 TpDataSessionAdditionalErrorInfo

Defines the Tagged Choice of Data Elements that specify additional Data Session error and Data Session error specific information.

Tag Element Type
TpDataSessionErrorType

Tag Element Value	Choice Element Type	Choice Element Name
P_DATA_SESSION_ERROR_UNDEFINED	NULL	Undefined
P_DATA_SESSION_ERROR_INVALID_ADDRESS	TpAddressError	DataSessionErrorInvalidAddress
P_DATA_SESSION_ERROR_INVALID_STATE	NULL	Undefined

### 8.5.2.12 TpDataSessionErrorType

Defines a specific Data Session error.

Name	Value	Description
P_DATA_SESSION_ERROR_UNDEFINED	0	Undefined; the method failed or was refused, but no specific reason can be given.
P_DATA_SESSION_ERROR_INVALID_ADDRESS	1	The operation failed because an invalid address was given
P_DATA_SESSION_ERROR_INVALID_STATE	2	The data session was not in a valid state for the requested operation

### 8.5.2.13 TpDataSessionFault

Defines the cause of the data session fault detected.

Name	Value	Description
P_DATA_SESSION_FAULT_UNDEFINED	0	Undefined
P_DATA_SESSION_USER_ABORTED	1	User has finalised the data session before any message could be sent by the application
P_DATA_SESSION_TIMEOUT_ON_RELEASE	2	This fault occurs when the final report has been sent to the application, but the application did not explicitly release data session object, within a specified time. The timer value is operator specific.
P_DATA_SESSION_TIMEOUT_ON_INTERRUPT	3	This fault occurs when the application did not instruct the gateway how to handle the call within a specified time, after the gateway reported an event that was requested by the application in interrupt mode. The timer value is operator specific.

### 8.5.2.14 TpDataSessionReleaseCause

Defines the Sequence of Data Elements that specify the cause of the release of a data session.

Sequence Element Name	Sequence Element Type
Value	TpInt32
Location	TpInt32

Note: the Value and Location are specified as in ITU-T recommendation Q.850.

### 8.5.2.15 TpDataSessionSuperviseVolume

Defines the Sequence of Data Elements that specify the amount of volume that is allowed to be transmitted for the specific connection.

Sequence Element Name	Sequence Element Type	Sequence Element Description
VolumeQuantity	TpInt32	This data type is identical to a TpInt32, and defines the quantity of the granted volume that can be transmitted for the specific connection. The volume specifies the sum of uplink and downlink transfer data volumes.
VolumeUnit	TpInt32	In Order to enlarge the range of the volume quantity value the exponent of a scaling factor ( $10^{\text{VolumeUnit}}$ ) is provided. When the unit is for example in kilobytes, VolumeUnit must be set to 3.

### 8.5.2.16 TpDataSessionSuperviseReport

Defines the responses from the data session control service for calls that are supervised. The values may be combined by a logical 'OR' function.

Name	Value	Description
P_DATA_SESSION_SUPERVISE_VOLUME_REACHED	01h	The maximum volume has been reached.
P_DATA_SESSION_SUPERVISE_DATA_SESSION_ENDED	02h	The data session has ended, either due to data session party to reach of maximum volume or calling or called release.
P_DATA_SESSION_SUPERVISE_MESSAGE_SENT	04h	A warning message has been sent.

### 8.5.2.17 TpDataSessionSuperviseTreatment

Defines the treatment of the call by the data session control service when the supervised volume is reached. The values may be combined by a logical 'OR' function.

Name	Value	Description
P_DATA_SESSION_SUPERVISE_RELEASE	01h	Release the data session when the data session supervision volume is reached.
P_DATA_SESSION_SUPERVISE_RESPOND	02h	Notify the application when the call supervision volume is reached.
P_DATA_SESSION_SUPERVISE_INFORM	04h	Send a warning message to the originating party when the maximum volume is reached. If data session release is requested, then the data session will be released following the message after an administered time period

### 8.5.2.18 TpDataSessionReport

Defines the Sequence of Data Elements that specify the data session report specific information.

Sequence Element Name	Sequence Element Type
MonitorMode	TpDataSessionMonitorMode
DataSessionEventTime	TpDateAndTime
DataSessionReportType	TpDataSessionReportType
AdditionalReportInfo	TpDataSessionAdditionalReportInfo

### 8.5.2.19 TpDataSessionAdditionalReportInfo

Defines the Tagged Choice of Data Elements that specify additional data session report information for certain types of reports.

	Tag Element Type	
	TpDataSessionReportType	

Tag Element Value	Choice Element Type	Choice Element Name
P_DATA_SESSION_REPORT_UNDEFINED	NULL	Undefined
P_DATA_SESSION_REPORT_CONNECTED	NULL	Undefined
P_DATA_SESSION_REPORT_DISCONNECT	TpDataSessionReleaseCause	DataSessionDisconnect

### 8.5.2.20 TpDataSessionReportRequest

Defines the Sequence of Data Elements that specify the criteria relating to data session report requests.

Sequence Element Name	Sequence Element Type
MonitorMode	TpDataSessionMonitorMode
DataSessionReportType	TpDataSessionReportType

### 8.5.2.21 TpDataSessionReportRequestSet

Defines a Numbered Set of Data Elements of TpDataSessionReportRequest.

### 8.5.2.22 TpDataSessionReportType

Defines a specific data session event report type.

Name	Value	Description
P_DATA_SESSION_REPORT_UNDEFINED	0	Undefined
P_DATA_SESSION_REPORT_CONNECTED	1	Data session established.
P_DATA_SESSION_REPORT_DISCONNECT	2	Data session disconnect requested by data session party

### 8.5.2.23 TpDataSessionEventCriteriaResultSetRef

Defines a reference to TpDataSessionEventCriteriaResultSet.

### 8.5.2.24 TpDataSessionEventCriteriaResultSet

Defines a set of TpDataSessionEventCriteriaResult.

### 8.5.2.25 TpDataSessionEventCriteriaResult

Defines a sequence of data elements that specify a requested call event notification criteria with the associated assignmentID.

Sequence Element Name	Sequence Element Type	Sequence Element Description
EventCriteria	TpDataSessionEventCriteria	The event criteria that were specified by the application.
AssignmentID	TpInt32	The associated assignmentID. This can be used to disable the notification.

## 8.6 Network User Location and User Status Data definitions

### 8.6.1 Interface Definitions

#### 8.6.1.1 IpAppUserStatus

Defines the address of an IpAppUserStatus Interface.

#### 8.6.1.2 IpAppUserStatusRef

Defines a reference to type IpAppUserStatus.

### 8.6.1.3 IpUserStatus

Defines the address of an IpUserStatus Interface.

### 8.6.1.4 IpAppUserLocationCamel

Defines the address of an IpAppUserLocationCamel Interface.

### 8.6.1.5 IpAppUserLocationCamelRef

Defines a reference to type IpAppUserLocationCamelRef.

### 8.6.1.6 IpUserLocationCamel

Defines the address of an IpUserLocationCamel Interface.

## 8.6.2 Common Data Definitions for Network User Location and User Status

The constants and types defined in the following sections are defined in the *org.threegpp.osa.mm* package.

### 8.6.2.1 TpGeographicalPosition

Defines the structure of data elements that specify a geographical position.

An “ellipsoid point with uncertainty shape” defines the horizontal location. The reference system chosen for the coding of locations is the World Geodetic System 1984 (WGS 84).

TypeOfUncertaintyShape describes the type of the uncertainty shape and Longitude/Latitude defines the position of the uncertainty shape. The following table defines the meaning of the data elements that describe the uncertainty shape for each uncertainty shape type.

Type of uncertainty shape	Uncertainty Outer Semi Major	Uncertainty Outer Semi Minor	Uncertainty Inner Semi Major	Uncertainty Inner Semi Minor	Angle Of Semi Major	Segment Start Angle	Segment End Angle
<b>None</b>	-	-	-	-	-	-	-
<b>Circle</b>	radius of circle	-	-	-	-	-	-
<b>Circle Sector</b>	radius of circle	-	-	-	-	start angle of circle segment	end angle of circle segment
<b>Circle Arc Stripe</b>	radius of outer circle	-	radius of inner circle	-	-	start angle of circle arc stripe	end angle of circle arc stripe
<b>Ellipse</b>	length of semi-major axis	length of semi-minor axis	-	-	rotation of ellipse measured clockwise from north	-	-
<b>Ellipse Sector</b>	length of semi-major axis	length of semi-minor axis	-	-	rotation of ellipse measured clockwise from north	start angle of ellipse segment	end angle of ellipse segment
<b>Ellipse Arc Stripe</b>	length of semi-major axis, outer ellipse	length of semi-minor axis, outer ellipse	length of semi-major axis, inner ellipse	length of semi-minor axis, inner ellipse	rotation of ellipse measured clockwise from north	start angle of ellipse arc stripe	end angle of ellipse arc stripe




Figure 8-1: Description of an Ellipse Arc

Structured Member Name	Structured Member Type
Longitude	TpFloat
Latitude	TpFloat
TypeOfUncertaintyShape	TpLocationUncertaintyShape
UncertaintyInnerSemiMajor	TpFloat
UncertaintyOuterSemiMajor	TpFloat
UncertaintyInnerSemiMinor	TpFloat
UncertaintyOuterSemiMinor	TpFloat
AngleOfSemiMajor	TpInt32
SegmentStartAngle	TpInt32
SegmentEndAngle	TpInt32

### 8.6.2.2 TpLocationUncertaintyShape

Defines the type of uncertainty shape.

Name	Value	Description
P_M_SHAPE_NONE	0	No uncertainty shape present.
P_M_SHAPE_CIRCLE	1	Uncertainty shape is a circle.
P_M_SHAPE_CIRCLE_SECTOR	2	Uncertainty shape is a circle sector.
P_M_SHAPE_CIRCLE_ARC_STRIPE	3	Uncertainty shape is a circle arc stripe.
P_M_SHAPE_ELLIPSE	4	Uncertainty shape is an ellipse.
P_M_SHAPE_ELLIPSE_SECTOR	5	Uncertainty shape is an ellipse sector.
P_M_SHAPE_ELLIPSE_ARC_STRIPE	6	Uncertainty shape is an ellipse arc stripe.

### 8.6.2.3 TpMobilityDiagnostic

Defines a diagnostic value that is reported in addition to an error by the Network User Location or User Status service capability feature.

Name	Value	Description
P_M_NO_INFORMATION	0	No diagnostic information present. Valid for all type of errors.
P_M_APPL_NOT_IN_PRIV_EXCEPT_LST	1	Application not in privacy exception list. Valid for ‘Unauthorised Application’ error.
P_M_CALL_TO_USER_NOT_SETUP	2	Call to user not set-up. Valid for ‘Unauthorised Application’ error.
P_M_PRIVACY_OVERRIDE_NOT_APPLIC	3	Privacy override not applicable. Valid for ‘Unauthorised Application’ error.
P_M_DISALL_BY_LOCAL_REGULAT_REQ	4	Disallowed by local regulatory requirements. Valid for ‘Unauthorised Application’ error.
P_M_CONGESTION	5	Congestion. Valid for ‘Position Method Failure’ error.
P_M_INSUFFICIENT_RESOURCES	6	Insufficient resources. Valid for ‘Position Method Failure’ error.
P_M_INSUFFICIENT_MEAS_DATA	7	Insufficient measurement data. Valid for ‘Position Method Failure’ error.
P_M_INCONSISTENT_MEAS_DATA	8	Inconsistent measurement data. Valid for ‘Position Method Failure’ error.
P_M_LOC_PROC_NOT_COMPLETED	9	Location procedure not completed. Valid for ‘Position Method Failure’ error.
P_M_LOC_PROC_NOT_SUPBY_USER	10	Location procedure not supported by user. Valid for ‘Position Method Failure’ error.
P_M_QOS_NOT_ATTAINEABLE	11	Quality of service not attainable. Valid for ‘Position Method Failure’ error.

### 8.6.2.4 TpMobilityError

Defines an error that is reported by the Network User Location or User Status service capability feature. A fatal error occurring during the life of periodic or triggered user location/status requests (`triggeredStatusReportErr`, `triggeredLocationReportErr` or `periodicLocationReportErr`) will terminate the request such that any particular request is allowed to generate at most one fatal error but possibly several non fatal errors.

Name	Value	Description	Fatal
P_M_OK	0	No error occurred while processing the request.	N/A
P_M_SYSTEM_FAILURE	1	System failure. The request can not be handled because of a general problem in the Network User Location or User Status SCF or the underlying network.	Yes
P_M_UNAUTHORIZED_NETWORK	2	Unauthorised network, The requesting network is not authorised to obtain the user's location or status.	No
P_M_UNAUTHORIZED_APPLICATION	3	Unauthorised application. The application is not authorised to obtain the user's location or status.	Yes
P_M_UNKNOWN_SUBSCRIBER	4	Unknown subscriber. The user is unknown, i.e. no such subscription exists.	Yes
P_M_ABSENT_SUBSCRIBER	5	Absent subscriber. The user is currently not reachable.	No
P_M_POSITION_METHOD_FAILURE	6	Position method failure. The Network User Location SCF failed to obtain the user's position.	No

### 8.6.2.5 TpMobilityStopAssignmentData

Defines the structure of data elements that specifies a request to stop whole or parts of an assignment. Assignments are used for periodic or triggered reporting of a user locations or statuses.

Observe that the parameter “users” is optional. If the parameter “stopScope” is set to `P_M_ALL_IN_ASSIGNMENT`, the parameter “stopScope” is undefined. If the parameter “stopScope” is set to `P_M_SPECIFIED_USERS`, then the assignment shall be stopped only for the users specified in the “users” collection.

Structure Element Name	Structure Element Type	Description
AssignmentId	TpSessionID	Identity of the session that shall be stopped.
StopScope	TpMobilityStopScope	Specify if only a part of the assignment or if whole the assignment shall be stopped.
Users	TpAddressSet	Optional parameter describing which users a stop request is addressing when only a part of an assignment is to be stopped.

### 8.6.2.6 TpMobilityStopScope

This enumeration is used in requests to stop mobility reports that are sent from the Network User Location service capability feature to an application.

Name	Value	Description
P_M_ALL_IN_ASSIGNMENT	0	The request concerns all users in an assignment.
P_M_SPECIFIED_USERS	1	The request concerns only the users that are explicitly specified in a collection.

### 8.6.3 Network User Location Data Definitions

The constants and types defined in the following sections are defined in the *org.threegpp.osa.mm.ul* package.

#### 8.6.3.1 TpLocationCellIDOrLAI

This data type is identical to a TString. It specifies the Cell Global Identification or the Location Area Identification (LAI).

The Cell Global Identification (CGI) is defined as the string of characters in the following format:

MCC–MNC–LAC–CI

where:

<b>MCC</b>	Mobile Country Code (three decimal digits)
<b>MNC</b>	Mobile Network Code (two or three decimal digits)
<b>LAC</b>	Location area code (four hexadecimal digits)
<b>CI</b>	Cell Identification (four hexadecimal digits)

The Location Area Identification (LAI) is defined as a string of characters in the following format:

MCC–MNC–LAC

where:

<b>MCC</b>	Mobile Country Code (three decimal digits)
<b>MNC</b>	Mobile Network Code (two or three decimal digits)
<b>LAC</b>	Location area code (four hexadecimal digits)

The length of the parameter indicates which format is used. See 3G TS 29.002 for the detailed coding.

#### 8.6.3.2 TpLocationTriggerCamel

Defines the structure of data elements that specifies the criteria for a triggered location report to be generated.

Structure Member Name	Structure Member Type	Description
UpdateInsideVlr	TpBoolean	Generate location report when it occurs an location update inside the current VLR area.
UpdateOutsideVlr	TpBoolean	Generate location report when the user moves to another VLR area.

#### 8.6.3.3 TpUserLocationCamel

Defines the structure of data elements that specifies the location of a mobile telephony user. Observe that if the statusCode is indicating an error, then neither geographicalPosition, timestamp, vlrNumber, locationNumber, cellIdOrLai nor their associated presense flags are defined.

Structure Member Name	Structure Member Type	Description
UserID	TpAddress	The address of the user.
StatusCode	TpMobilityError	Indicator of error.
GeographicalPositionPresent	TpBoolean	Flag indicating if the geographical position is present.
GeographicalPosition	TpGeographicalPosition	Specification of a position and an area of uncertainty.
TimestampPresent	TpBoolean	Flag indicating if the timestamp is present.
Timestamp	TpDateAndTime	Timestamp indicating when the location information was attained .
VlrNumberPresent	TpBoolean	Flag indicating if the VLR number is present.
VlrNumber	TpAddress	Current VLR number for the user.

VocationNumberPresent	TpBoolean	Flag indicating if the location number is present.
LocationNumber <sup>2</sup>	TpAddress	Current location number.
CellIdOrLaiPresent	TpBoolean	Flag indicating if cell-id or LAI of the user is present.
CellIdOrLai	TpLocationCellIDOrLAI	Cell-id or LAI of the user.

### 8.6.3.4 TpUserLocationCamelSet

Defines a collection of TUserLocationCamel

## 8.7 User Status Data Definitions

The constants and types defined in the following sections are defined in the *org.threegpp.osa.mm.us* package.

### 8.7.1.1 TpUserStatus

Defines the structure of data elements that specifies the identity and status of a user.

Structure Element Name	Structure Element Type	Description
UserID	TpAddress	The user address.
StatusCode	TpMobilityError	Indicator of error.
Status	TpUserStatusIndicator	The current status of the user.

### 8.7.1.2 TpUserStatusSet

Defines a collection of TUserStatus.

### 8.7.1.3 TpUserStatusIndicator

Defines the status of a user.

Name	Value	Description
P_US_REACHABLE	0	User is reachable
P_US_NOT_REACHABLE	1	User is not reachable
P_US_BUSY <sup>3</sup>	2	User is busy (only applicable for interactive user status request, not when triggers are used)

## 8.8 Terminal Capabilities Data Definitions

### 8.8.1 Interface Definitions

#### 8.8.1.1 IpTerminalCapabilities

Defines the address of an IpTerminalCapabilities Interface.

#### 8.8.1.2 IpTerminalCapabilitiesRef

Defines a reference to type IpTerminalCapabilities

<sup>2</sup> The location number is the number to the MSC or in rare cases the roaming number.

<sup>3</sup> Only applicable to mobile (Wireless) telephony users.

## 8.8.2 Terminal Capabilities Data Definitions

The constants and types defined in the following sections are defined in the *org.threegpp.osa.termcap* package.

### 8.8.2.1 terminalIdentity

Identifies the terminal.

Name	Type	Documentation
terminalIdentity	TpString	Identifies the terminal. It may be a logical address known by the WAP Gateway/PushProxy.

### 8.8.2.2 TpTerminalCapabilities

This data type is a Sequence\_of\_Data\_Elements that describes the terminal capabilities. It is a structured type that consists of:

Sequence Element Name	Sequence Element Type	Documentation
StatusCode	TpBoolean	Indicates whether or not the terminalCapabilities are available.
TerminalCapabilities	TpServicePropertyList	Specifies the latest available capabilities of the user's terminal. This information, if available, is returned as CC/PP headers as specified in W3C [12] and adopted in the WAP Uaprof specification [13]. It contains URLs; terminal attributes and values, in RDF format; or a combination of both.

### 8.8.2.3 TpTerminalCapabilitiesError

Defines an error that is reported by the Terminal Capabilities SCF.

Name	Value	Description
P_TERMCAP_ERROR_UNDEFINED	0	Undefined.
P_TERMCAP_INVALID_TERMINALID	1	The request can not be handled because the terminal id specified is not valid.
P_TERMCAP_SYSTEM_FAILURE	2	System failure. The request cannot be handled because of a general problem in the terminal capabilities service or the underlying network.

## 9 IDL Interface Definitions

The OSA API definitions have been divided into several CORBA modules. The common data definitions are placed in the root module while each of the specific service capability feature API definitions are being assigned their own module directly under that root. Each specific SCF functions, like User Status, have their data and interface definitions collocated. This structure has the advantage that explicit scoping is kept to a minimum.

The IDLs defined for the specific SCFs assumes that the OSA common definitions (interfaces and data) are provided in the org.threegpp.osa module within a file name called OSA.idl

Module Name	Description	IDL file name
org.threegpp.osa	Common data/interface definitions	OSA.idl
org.threegpp.osa.mm	Common mobility data definitions (root)	MM.idl
org.threegpp.osa.mm.ul	Network User Location (UL)	MMUL.idl
org.threegpp.osa.mm.us	User Status (US)	MMUS.idl
org.threegpp.osa.cc	Call Control	CC.idl
org.threegpp.osa.ui	User Interaction	UI.idl
org.threegpp.osa.termcap	Terminal Capabilities	TERMCAP.idl

### 9.1 Generic IDL

```
#ifndef __OSA_DEFINED
#define __OSA_DEFINED

module org
{
    module threegpp
    {
        module osa
        {
            /**
             * Primitive data types
             */
            typedef boolean TpBoolean;      // Defines a Boolean data type
            typedef long TpInt32;          // Defines a signed 32 bit integer
            typedef float TpFloat;         // Defines a single precision real number.
            typedef string TpString;       // Defines a string comprising length and data.

            /**
             * Primitive based OSA datatypes
             */

            typedef TpInt32 TpDuration;    // This data type is a TpInt32 representing a
                                         // time interval in milliseconds. A value of "-1" defines
                                         // an indefinite duration.
        }
    }
}
```

```

        // infinite duration and a value of "-2" represents default
        // duration.

typedef TpInt32 TpSessionID; // Defines a network unique session ID. OSA
                            // uses this ID to identify sessions, e.g. call or call leg
                            // sessions, within an object implementing an interface
                            // capable of handling multiple sessions. For the different
                            // OSA service capability feature, the sessionIDs are unique
                            // only in the context of a manager instantiation (e.g., within
                            // the context of one generic call control manager). As such
                            // if an application creates two instances of the same SCF
                            // manager it shall use different instantiations of the
                            // callback objects which implement the callback interfaces.

typedef TpInt32 TpAssignmentID; // This data type is identical to a TpInt32. It
                                // specifies a number which identifies an individual
                                // event notification enabled by the application or
                                // OSA service capability feature.

typedef sequence < TpSessionID> TpSessionIDSet;

// Defines the general Parlay exception values

enum TpGeneralExceptionType
{
    P_RESULT_INFO_UNDEFINED,      // No further information present
    P_INVALID_APPLICATION_ID,    // Invalid application ID
    P_INVALID_CLIENT_CAPABILITY, // Invalid client capability
    P_INVALID AGREEMENT_TEXT,    // Invalid agreement text
    P_INVALID_SIGNING_ALGORITHM, // Invalid signing algorithm
    P_INVALID_INTERFACE_NAME,    // Invalid interface name
    P_INVALID_SERVICE_ID,        // Invalid service capability feature ID
    P_INVALID_EVENT_TYPE,        // Invalid event type
    P_SERVICE_NOT_ENABLED,       // The SCF ID does not correspond
                                // to a SCF that has been enabled
    P_INVALID_ASSIGNMENT_ID,      // The assignment ID does not
                                // correspond to one of the valid assignment IDs
    P_INVALID_PARAMETER,         // The method has been called with an
                                // invalid parameter
    P_INVALID_PARAMETER_VALUE,   // A method parameter has an invalid value
    P_PARAMETER_MISSING,         // A required parameter has not been
                                // specified in the method call
    P_RESOURCES_UNAVAILABLE,     // The required resources in the
                                // network are not available
    P_TASK_REFUSED,              // The requested method has been refused
}
```

```

P_TASK_CANCELLED,           // The requested method has been cancelled
P_INVALID_DATE_TIME_FORMAT, // Invalid date and time format provided
P_NO_CALLBACK_ADDRESS_SET,  // The requested method has been refused
                           // because no callback address is set
P_INVALID_TERMINATION_TEXT, // Invalid termination text
P_INVALID_SERVICE_TOKEN,   // The SCF token does not correspond to a
                           // token that had been issued, or the issued token
                           // has expired.
P_INVALID_AUTHENTICATION,  // The client has not been correctly authenticated
P_INVALID_SERVICE_PROPERTY, // Invalid service capability feature property.
P_METHOD_NOT_SUPPORTED     // The method is not allowed or supported within
                           // the context of the current SCF agreement.

};

exception TpGeneralException
{
    TpGeneralExceptionType exceptionType;
};

// Defines the GCCS OSA exception values
enum TpGCCSExceptionType
{
    P_GCCS_SERVICE_INFORMATION_MISSING, // Information relating to the Call
                                       // Control SCF could not be found
    P_GCCS_SERVICE_FAULT_ENCOUNTERED, // Fault detected in the Call Control SCF
    P_GCCS_UNEXPECTED_SEQUENCE,    // Unexpected sequence of methods, i.e.,
                                   // the sequence does not match the specified
                                   // state diagrams for the call or the call leg.
    P_GCCS_INVALID_ADDRESS,        // Invalid address specified
    P_GCCS_INVALID_STATE,         // Invalid state specified
    P_GCCS_INVALID_CRITERIA,     // Invalid criteria specified
    P_GCCS_INVALID_NETWORK_STATE, // Although the sequence of method calls is
                                   // allowed by the OSA gateway, the underlying
                                   // protocol can not support it. E.g., in some
                                   // protocols some methods are only allowed by
                                   // the protocol, when the call processing is
                                   // suspended, e.g., after reporting an event
                                   // that was monitored in interrupt mode.

    P_GCCS_NETWORK_DEASSIGN // The relation between the network and the OSA
                           // gateway is terminated. Therefore, the gateway
                           // can no longer influence the call. This can happen
                           // after the last requested report is sent to the

```

```

        // application. To prevent this error, the application
        // should ensure that it has requested events which
        // are not yet reported.

};

exception TpGCCSEException
{
    TpGCCSEExceptionType exceptionType;
};

// Defined the GUIS OSA exception values
enum TpGUISEExceptionType
{
    P_GUIS_INVALID_CRITERIA, // Invalid criteria specified
    P_GUIS_ILLEGAL_ID,      // Information id specified is invalid
    P_GUIS_ID_NOT_FOUND,    // A legal information id is not known to the User
                           // Interaction SCF
    P_GUIS_ILLEGAL_RANGE,   // The values for minimum and maximum collection
                           // length are out of range.

    P_GUIS_INVALID_COLLECTION_CRITERIA, // Invalid collection criteria specified
    P_GUIS_NETWORK_DEASSIGN, // The relation between the network and the OSA
                           // gateway is terminated. Therefore, the gateway
                           // can no longer perform UI operations. This can
                           // happen after the last requested report is sent
                           // to the application. To prevent this error, the
                           // application should ensure that it has requested
                           // events which are not yet reported.

    P_GUIS_INVALID_NETWORK_STATE // Although the sequence of method calls is
                           // allowed by the OSA gateway, the underlying
                           // protocol can not support it. E.g., in some
                           // protocols some methods are only allowed by
                           // the protocol, when the call processing is
                           // suspended, e.g., after reporting an event
                           // that was monitored in interrupt mode.

};

exception TpGUISEException
{
    TpGUISEExceptionType exceptionType;
};

```

```
/*********************************************
***** Date and Time related data definitions *****
/*********************************************  
  
// This data type is identical to a TpString. It specifies the data in  
// accordance with International Standard ISO 8601. This is defined as the  
// string of characters in the following format:  
//  
// YYYY-MM-DD  
// where the date is specified as:  
//  
//     YYYY    four digits year  
//     MM      two digits month  
//     DD      two digits day  
// The date elements are separated by a hyphen character (-).  
typedef TpStringTpDate;  
  
// This data type is identical to a TpString. It specifies the time in accordance  
// with International Standard ISO 8601. This is defined as the string of  
// characters in the following format:  
//  
//     HH:MM:SS.mmmm  
// or  
//     HH:MM:SS.mmmmZ  
// where the time is specified as:  
//  
//     HH  two digits hours (24h notation)  
//     MM  two digits minutes  
//     SS  two digits seconds  
//     mmmm three digits fractions of a second (i.e. milliseconds)  
// The time elements are separated by a colon character (:).The date and time  
// are separated by a space. Optionally, a capital letter Z may be appended  
// to the time field to indicate Universal Time (UTC). Otherwise, local time  
// is assumed.  
typedef TpStringTpTime;  
  
// This data type is identical to TosaString. It specifies the data and time  
// in accordance with International Standard ISO 8601. This is defined as the  
// string of characters in the following format:  
//  
//     YYYY-MM-DD HH:MM:SS.mmmm  
// or  YYYY-MM-DD HH:MM:SS.mmmmZ  
//  
// Example:  
//  
//     The 4 December 1998, at 10:30 and 15 seconds is encoded as the string:  
//  
//     1998-12-04 10:30:15.000
```

```

//      for local time, or in UTC it would be:
//      1998-12-04 10:30:15.000Z

typedef TpString TpDateAndTime;

/********************* Address related data definitons ********************/
// Defines whether an address can be presented to an end user
enum TpAddressPresentation
{
    P_ADDRESS_PRESENTATION_UNDEFINED,           // Undefined
    P_ADDRESS_PRESENTATION_ALLOWED,            // Presentation Allowed
    P_ADDRESS_PRESENTATION_RESTRICTED,         // Presentation Restricted
    P_ADDRESS_PRESENTATION_ADDRESS_NOT_AVAILABLE // Address not available for
                                                // presentation
};

// Defines whether an address has been screened by the application
enum TpAddressScreening
{
    P_ADDRESS_SCREENING_UNDEFINED,              // Undefined
    P_ADDRESS_SCREENING_USER_VERIFIED_PASSED,   // user provided address verified
                                                // and passed
    P_ADDRESS_SCREENING_USER_NOT_VERIFIED,       // user provided address not verified
    P_ADDRESS_SCREENING_USER_VERIFIED_FAILED,     // user provided address verified and
                                                // failed
    P_ADDRESS_SCREENING_NETWORK                // Network provided address
};

// Defines the address plan (or numbering plan) used. It is also used to indicate
// whether an address is actually defined in a TAddress data element
enum TpAddressPlan
{
    P_ADDRESS_PLAN_NOT_PRESENT,    // No Address Present
    P_ADDRESS_PLAN_UNDEFINED,      // Undefined
    P_ADDRESS_PLAN_IP,            // IP
    P_ADDRESS_PLAN_MULTICAST,     // Multicast
    P_ADDRESS_PLAN_UNICAST,       // Unicast
    P_ADDRESS_PLAN_E164,          // E.164
    P_ADDRESS_PLAN_E164_MOBILE,    // E.164 Mobile
    P_ADDRESS_PLAN_AESPA          // AESPA
};

```

```

P_ADDRESS_PLAN_URL,           // URL
P_ADDRESS_PLAN_NSAP,          // NSAP
P_ADDRESS_PLAN_SMTP,          // SMTP
P_ADDRESS_PLAN_NOT_USED,
P_ADDRESS_PLAN_X400           // X.400
};

// Defines the reasons why an address is invalid.

enum TpAddressError
{
    P_ADDRESS_INVALID_UNDEFINED,      // Undefined error
    P_ADDRESS_INVALID_MISSING,        // Mandatory address not present
    P_ADDRESS_INVALID_MISSING_ELEMENT, // Mandatory address element not present
    P_ADDRESS_INVALID_OUT_OF_RANGE,   // Address is outside of the valid range
    P_ADDRESS_INVALID_INCOMPLETE,     // Address is incomplete
    P_ADDRESS_INVALID_CANNOT_DECODE  // Address cannot be decoded
};

// Defines the structure of data elements that specifies an address

struct TpAddress
{
    TpAddressPlan      plan;
    TpString           astring;
    TpString           name;
    TpAddressPresentation presentation;
    TpAddressScreening screening;
    TpString           subAddressString;
};

// Defined a collection of TpAddress elements

typedef sequence <TpAddress> TpAddressSet;

// Defined a collection of TpAddress elements

typedef TpAddress TpAddressRange;

// This data type is identical to a TpString and contains a URL address.

typedef TpString TpURL;

// This data type is identical to a TpString. It specifies price information.

// This is defined as the string of characters (digits) in the following format:
//      DDDDDDD.DD

typedef TpString TpPrice;

```

```

struct TpChargePerTime {
    TpInt32 InitialCharge; /*Initial charge amount (in currency units * 0.0001)*/
    TpInt32 CurrentChargePerMinute; /* Current tariff (in currency units * 0.0001)*/
    TpInt32 NextChargePerMinute; /* Next tariff (in currency units * 0.0001) after tariff switch
Only used in setAdviceOfCharge()*/
};

enum TpAoCOrderCategory {
    P_CHARGE_ADVICE_INFO, /* Set of GSM Charge Advice Information elements according to 3G TS 22.024*/
    P_CHARGE_PER_TIME, /* Charge per time*/
    P_CHARGE_NETWORK /* Operator specific charge plan specification, e.g. charging table name /
charging table entry*/
};

/* Defines the Sequence of Data Elements that specify theCharging Advice Information elements
according to 3G TS 22.024.*/
struct TpCAIElements {

TpInt32 UnitsPerInterval; /* Units per interval */
TpInt32 SecondsPerTimeInterval; /* Seconds per time interval */
TpInt32 ScalingFactor; /* Scaling factor */
TpInt32 UnitIncrement; /* Unit increment */
TpInt32 UnitsPerDataInterval; /* Units per data interval */
TpInt32 SegmentsPerDataInterval; /* Segments per data interal */
TpInt32 InitialSecsPerTimeInterval; /* Initial secs per time interval */
};

struct TpChargeAdviceInfo {
    TpCAIElements CurrentCAI ; /* Current tariff*/
    TpCAIElements NextCAI ; /* Next tariff after tariff switch*/
};

/* Defines the Tagged Choice of Data Elements that specify the charge plan */
union TpAoCOrder switch(TpAoCOrderCategory) {
    case P_CHARGE_ADVICE_INFO:
        TpChargeAdviceInfo ChargeAdviceInfo;
    case P_CHARGE_PER_TIME:
        TpChargePerTime ChargePerTime;
    case P_CHARGE_NETWORK:
        TpString NetworkCharge;
};

```

```

};

struct TpAoCInfo {
    TpAoCOrder ChargeOrderType; /* Charge order*/
    TpString Currency; /* Currency unit according to ISO-4217:1995*/
};

/*********************************************
//                                base OSA interface
/********************************************/

// All application, framework and service capability features inherit
// from the following interface. This API Base Interface does not provide any
// additional methods.

interface IpOsa
{
};

// All service capability feature interfaces inherit from the following interface.

interface IpService : IpOsa
{
    // This method specifies the reference address of the callback interface
    // that a SCF uses to invoke methods on the application.

    void setCallback(in IpOsa appInterface) raises(TpGeneralException);
};

};

};

};

#endif

```

## 9.2 Framework IDL

### 9.2.1 Common Data Types for the Framework

```
#include <OSA.idl>

module org{
module threegpp{
module osa{

module fw{
```

```

typedef TpStringTpClientAppID;           // Identifies the client appl to the framework.

typedef sequence <TpClientAppID> TpClientAppIDList;

typedef TpStringTpEntOpID;

typedef sequence <TpEntOpID> TpEntOpIDList;

typedef TpStringTpServiceID;    // A string of characters, generated automatically by the
                               // Framework and comprising a TpUniqueServiceNumber,
                               // TpServiceNameString, and a number of relevant
                               // TpServiceSpecString, concatenated using a forward
                               // separator (/), that uniquely identifies an instance of a
                               // SCF interface.

typedef sequence <TpServiceID> TpServiceIDList;

typedef TpStringTpServiceNameString; // Uniquely identifies the name of an SCF
                                   // interface. For OSA release 99 the following
                                   // values have been defined: NULL (no SCF name),
                                   // P_CALL_CONTROL, P_USER_INTERACTION,
                                   // P_USER_LOCATION, P_TERMINAL_CAPABILITIES and
                                   // P_USER_STATUS.

typedef TpStringTpServiceSpecString; // Uniquely identifies the name of a SCF
                                   // specialisation interface. For OSA release 99
                                   // the following values have been defined: NULL
                                   // (no SCF specialisation) and P_CALL.

typedef TpStringTpUniqueServiceNumber; // A string of characters that represents a
                                      // unique number.

enum TpServicePropertyMode {
    NORMAL,                         // The value of the corresponding SCF property type may optionally be
                                      // provided.

    MANDATORY,                       // The value of the corresponding SCF property type must be provided
                                      // at SCF registration.

    READONLY,                         // The value of the corresponding SCF property is optional, but once
                                      // given a value it may not be modified.

    MANDATORY_READONLY               // The value of the corresponding SCF property type must be provided
                                      // and may not be modified subsequently.

};


```

```

typedef TpString      TpServicePropertyName;

typedef TpString      TpServicePropertyName;

typedef sequence <TpServicePropertyName>  TpServicePropertyNameList;

typedef TpString      TpServicePropertyValue;

typedef sequence <TpServicePropertyValue>  TpServicePropertyValueList;

struct TpServiceProperty {           // Describes a SCF property
    TpServicePropertyName      ServicePropertyName;
    TpServicePropertyValueList ServicePropertyValueList;
    TpServicePropertyMode      ServicePropertyMode;
};

typedef sequence <TpServiceProperty>  TpServicePropertyList;

typedef TpString      TpServiceTypeName;

typedef sequence <TpServiceTypeName>  TpServiceTypeNameList;

struct TpService {           // Describes a registered SCF.
    TpServiceID      ServiceID;
    TpServicePropertyList ServicePropertyList;
};

typedef sequence <TpService>  TpServiceList;

struct TpServiceDescription {           // Describes the properties of a registered SCF.
    TpServiceTypeName      ServiceTypeName;
    TpServicePropertyList ServicePropertyList;
};

struct TpPropertyStruct {           // Describes a SCF property.
    TpServiceTypeName      ServicePropertyName;
    TpServicePropertyMode      ServicePropertyMode;
    TpServicePropertyTypeNames ServicePropertyTypeNames;
};

typedef sequence <TpPropertyStruct>  TpPropertyStructList;

```

```
    struct TpServiceTypeDescription {           // Describes a SCF type.  
        TpPropertyStructList      PropertyStructList;  
        TpServiceTypeNameList     ServiceTypeNameList;  
        TpBoolean                EnabledOrDisabled;  
    };  
};};};};};
```

### 9.2.2 Service Discovery IDL

```
#include <fw.idl>
```

```
module org{  
    module threeGPP{  
        module osa{  
            module fw{  
                module discovery{
```

```
/* The Service Discovery Framework interface is used by the client application to  
know what types of services are supported by the Framework, and what are their  
properties; and to obtain the services its subscription allows access to. */  
  
interface IpServiceDiscovery : IpOsa {
```

```
/* This method is invoked by the client application to obtain the names of all service
types that are in the Framework repository. */
void listServiceTypes (
    out TpServiceTypeNameList listTypes      // The names of the requested service types.
) raises (TpGeneralException);
```

```
/* This method is invoked by the client application to obtain the detailed description of
a particular service type. */

void describeServiceType (
    in TpServiceTypeName name,                                // Identifies the service
                                                       // type to be described.

    out TpServiceTypeDescription serviceTypeDescription      // Describes the specified
                                                               // service type.

) raises (TpGeneralException);
```

### 9.2.3 Trust and Security Management IDL

```

typedef TpString      TpAuthType;          // The type of authentication mechanism requested by the
                                           // client. For OSA release 99 the following values have
                                           // been defined: NULL (indicates OSA authentication),
                                           // P_AUTHENTICATION (indicates use of the OSA
                                           // authentication interfaces.

typedef TpString  TpAuthCapability;    // The authentication capabilities that could be supported
                                           // by the OSA. For OSA release 99 the following values
                                           // have been defined: NULL (indicates no client
                                           // capabilities, P_DES_56, P_RSA_512 and P_RSA_1024).

typedef TpString      TpAuthCapabilityList; // A string of multiple TpAuthCapability
                                           // concatenated using a commas.

typedef TpString      TpInterfaceName;   // Identifies the names of the framework SCFs that are be
                                           // supported by the OSA API. For release 99 these are NULL,
                                           // P_DISCOVERY, P_OAM, P_TRUST_AND_SECURITY_MANAGEMENT
                                           // P_INTEGRITY_MANAGEMENT.

struct TpServiceAccessControl {
    TpString      Policy;           // Access control policy information controlling access to the
                                   // service feature.
    TpString      TrustLevel;       // The level of trust that the network operator has assigned to the
                                   // client application.
};

typedef TpString      TpServiceToken;   // Uniquely identifies a SCF.

struct TpSignatureAndServiceMgrRef {
    TpString      DigitalSignature; // The digital signature of the Framework for the service
                                   // agreement.
    IpOsa        ServiceMgrInterface;
};

typedef TpString      TpSigningAlgorithm; // Identifies the signing algorithm that must be
                                           // used. For OSA release 99 the follwing values have
                                           // been defined: NULL (indicates no signing algorithm
                                           // is required), P_MD5_RSA_512 and P_MD5_RSA_1024.

```

```

typedef TpString      TpFwID;

struct TpFwAuth {
    TpFwID    FwID;
    IpOsa   FwAuthInterface;
};

/*********************************************
//                                         Interface definitions //
/********************************************/


/* The Initial Framework interface is used by the client application to initiate the mutual
authentication with the Framework and, when this is finished successfully, to request access
to it. */

interface IpInitial : IpOsa {

    /* This method is invoked by the client application to start the process of mutual
    authentication with the framework, and request the use of a specific authentication method.
    */

    void initiateAuthentication (
        in TpClientAppID clientAppID,           // Identifies the client to the framework.
        in TpAuthType authType,                 // Allows the client application to request a
                                                // specific type of authentication mechanism.
        in IpOsa appAuthInterface,             // Provides a reference to the client application
                                                // authentication interface.
        out TpFwAuth fwAuthInterface          // Provides a framework identifier, and a reference
                                                // to framework authentication interface.

    ) raises (TpGeneralException);

    /* This method is invoked by the client application, once mutual authentication is
    achieved, to request access to the framework and specify the type of access desired. */
    void requestAccess (
        in TpAccessType accessType,            // Identifies the type of access interface requested by
                                                // the client application.
        in IpOsa appAccessInterface,          // Provides a reference to the access interface of the
                                                // client application.
        out IpOsa fwAccessInterface          // Provides a reference to call the access interface of
                                                // the framework.

    ) raises (TpGeneralException);
}

```

```

};

/* The Access Framework interface is used by the client application to perform the mechanisms
necessary for it to obtain access to SCFs. */

interface IpAccess : IpOsa {

    /* This method is invoked by the client application to obtain interface references to other
framework interfaces. */

    void obtainInterface (
        in TpInterfaceName interfaceName,      // The name of the framework interface to which a
                                                // reference to the interface is requested.

        out IpOsa fwInterface              // The requested interface reference.

    ) raises (TpGeneralException);

    /* This method is invoked by the client application to obtain interface references to other
framework interfaces, when it is required to supply a callback interface to the framework.
 */

    void obtainInterfaceWithCallback (
        in TpInterfaceName interfaceName,      // The name of the framework interface to which
                                                // a reference to the interface is requested.

        in IpOsa appInterface,                // This is the reference to the client application
                                                // interface which is used for callbacks.

        out IpOsa fwInterface              // The requested interface reference.

    ) raises (TpGeneralException);

    /* This method may be invoked by the client application to check whether it has been
granted permission to access the specified SCF and, if granted, the level of trust that
will be applied. */

    void accessCheck (
        in TpString securityContext,          // A group of security relevant
                                                // attributes.

        in TpString securityDomain,           // The security domain in which
                                                // the client application is
                                                // operating.

        in TpString group,                  // Used to define the access
                                                // rights associated with all
                                                // clients that belong to that
                                                // group.

        in TpString serviceAccessTypes,       // Defined by the specific
                                                // requirements of the SCF.
    );
}

```

```

                                // security model in use.

out TpServiceAccessControl serviceAccessControl           // The access control policy
                                                // information controlling
                                                // access to the service
                                                // capability feature, and the
                                                // trustLevel that the network
                                                // operator has assigned to the client
                                                // application.

) raises (TpGeneralException);

/* This method is invoked by the client application to identify the SCF that it wishes
to use. */

void selectService (
in TpServiceID serviceID,                               // Identifies the SCF.
in TpServicePropertyList serviceProperties,           // List the properties that the SCF
                                                    // should support.

out TpServiceToken serviceToken                         // A free format text token returned by
                                                    // the framework, which can be signed as
                                                    // part of a service agreement.

) raises (TpGeneralException);

/* This method is invoked by the client application to request that the framework sign an
agreement on the SCF, which allows the client application to use the SCF. */
void signServiceAgreement (
in TpServiceToken serviceToken,                         // Used to identify the SCF
                                                    // instance requested by the
                                                    // client application.

in TpString agreementText,                            // The agreement text to be
                                                    // signed by the framework.

in TpSigningAlgorithm signingAlgorithm,               // The algorithm used to compute
                                                    // the digital signature.

out TpSignatureAndServiceMgrRef signatureAndServiceMgr // A reference to a structure
                                                    // that contains the digital
                                                    // signature of the framework
                                                    // for the service agreement,
                                                    // and a reference to the
                                                    // SCF manager interface of
                                                    // the SCF.

) raises (TpGeneralException);

```

```

/* This method is invoked by the client application to terminate an agreement for the
specified SCF. */

void terminateServiceAgreement (
    in TpServiceToken serviceToken,           // Identifies the service agreement to be terminated.
    in TpString terminationText,             // Describes the reason for the termination of the
                                            // service agreement.
    in TpString digitalSignature           // Used by the framework to check that the
                                            // terminationText has been signed by the client.
) raises (TpGeneralException);

/* This method is invoked by the client application to end the access session
with the Framework. */

void endAccess () raises (TpGeneralException);

};

/* The Access client application interface is used by the Framework to perform the steps that
are necessary in order to allow it to SCF access. */

interface IpAppAccess : IpOsa {

    /* This method is invoked by the Framework to request that client application sign an
agreement on a specified SCF. */

    void signServiceAgreement (
        in TpServiceToken serviceToken,           // Identifies the SCF instance to which
                                                // this service agreement corresponds.
        in TpString agreementText,              // Agreement text that has to be signed by the
                                                // client application.
        in TpSigningAlgorithm signingAlgorithm, // Algorithm used to compute the digital
                                                // signature.
        out TpString digitalSignature          // Signed version of a hash of the service
                                                // token and agreement text given by the
                                                // framework.
    ) raises (TpGeneralException);

    /* This method is invoked by the Framework to terminate an agreement for a specified
SCF. */

    void terminateServiceAgreement (
        in TpServiceToken serviceToken,           // Identifies the SCF agreement to be terminated.
    ) raises (TpGeneralException);
}

```

```

    in TpString terminationText,           // Describes the reason for the termination.
    in TpString digitalSignature        // Used by the Framework to confirm its identity to the
                                         // client.

) raises (TpGeneralException);

/* This method is invoked by the Framework to end the client application's access session
with the framework. */

void terminateAccess (
    in TpString terminationText,           // Describes the reason for the termination of
                                         // the access session.
    in TpSigningAlgorithm signingAlgorithm, // The algorithm used to compute the digital
                                         // signature.
    in TpString digitalSignature          // Used by the Framework to confirm its
                                         // identity to the client.

) raises (TpGeneralException);

};

*/

```

```

/* The Authentication Framework interface is used by client application to perform its part of
the mutual authentication process with the Framework necessary to be allowed to use any of the
other interfaces supported by the Framework. */

interface IpAuthentication : IpOsa {

    /* This method is invoked by the client application to start the authentication process,
informed the Framework of the authentication mechanisms it supports, and be informed by its
of its preferred choice. */

    void selectAuthMethod (
        in TpAuthCapabilityList authCapability,      // Informs the Framework of the authentication
                                                   // mechanisms supported by the client
                                                   // application.
        out TpAuthCapability prescribedMethod        // Indicates the mechanism preferred by the
                                                   // framework.

    ) raises (TpGeneralException);

    /* This method is invoked by the client application to authenticate the framework using the
mechanism indicated in the parameter prescribedMethod. */

    void authenticate (
        in TpAuthCapability prescribedMethod,        // Specifies the method accepted by that the

```

#### 9.2.4 Integrity Management IDL

```
#include <fw.idl>
```

```

module org{
  module threegpp{
    module osa{
      module fw{
        module integrity{

          /***** Data definitions ****/
          // Data definitions
          /****/


          typedef TpString     TpActivityTestRes;           // An implementation specific result, whose values
                                                       // are Framework provider specific.

          struct TpTimeInterval {           // A time interval.
            TpDateAndTime     StartTime;
            TpDateAndTime     StopTime;
          };

          enum TpInterfaceFault {           // The cause of the interface fault detected.
            INTERFACE_FAULT_UNDEFINED,      // Undefined.
            INTERFACE_FAULT_LOCAL_FAILURE,   // A fault in the local API software or hardware has been
                                             // detected.
            INTERFACE_FAULT_GATEWAY_FAILURE, // A fault in the gateway API software or hardware has been
                                             // detected.
            INTERFACE_FAULT_PROTOCOL_ERROR   // An error in the protocol used on the client-gateway link
                                             // has been detected.
          };

          struct TpFaultStatsSet {           // Statistics on a per fault type basis.
            TpInterfaceFault   Fault;
            TpInt32             Occurrences;           // The number of separate instances of this fault
                                                       // during the period.
            TpInt32             MaxDuration;          // The duration in seconds of the longest fault.
            TpInt32             TotalDuration;         // The cumulative total during the period.
            TpInt32             NumberOfClientsAffected; // Those informed of the fault by the Framework.
          };

          struct TpFaultStatsRecord {         // The set of fault information records to be returned for the
                                             // requested time period.
        }
      }
    }
  }
}

```

```

TpTimeInterval      Period;
TpFaultStatsSet    FaultRecords;
};

typedef TpInt32     TpActivityTestID;           // Used as a token to match activity test requests
                                                // with their results.

enum TpSvcUnavailReason {                      // The reason why a SCF is unavailable.
    SERVICE_UNAVAILABLE_UNDEFINED,             // Undefined.
    SERVICE_UNAVAILABLE_LOCAL_FAILURE,         // The local API software or hardware has failed.
    SERVICE_UNAVAILABLE_GATEWAY_FAILURE,       // The gateway API software or hardware has failed.
    SERVICE_UNAVAILABLE_OVERLOADED,            // The SCF is fully overloaded.
    SERVICE_UNAVAILABLE_CLOSED                // The SCF has closed itself.
};

enum TpAPIUnavailReason {                      // The reason why the API is unavailable.
    API_UNAVAILABLE_UNDEFINED,                // Undefined.
    API_UNAVAILABLE_LOCAL_FAILURE,            // The local API software or hardware has failed.
    API_UNAVAILABLE_GATEWAY_FAILURE,          // The gateway API software or hardware has failed.
    API_UNAVAILABLE_OVERLOADED,               // The gateway is fully overloaded.
    API_UNAVAILABLE_CLOSED,                  // The gateway has closed itself.
    API_UNAVAILABLE_PROTOCOL_FAILURE         // The protocol used on the client-gateway link has failed.
};

enum TpLoadLevel {                            // The load level values.
    LOAD_LEVEL_NORMAL,                        // Normal load.
    LOAD_LEVEL_OVERLOAD,                     // Overload.
    LOAD_LEVEL_SEVERE_OVERLOAD              // Severe overload.
};

struct TpLoadThreshold{ // The load threshold value.
    TpFloat      LoadThreshold;
};

struct TpLoadInitVal { // The pair of load level and associated load threshold values.
    TpLoadLevel   LoadLevel;
    TpLoadThreshold LoadThreshold;
};

```

```

struct TpLoadPolicy {      // The load balancing policy.
    TpString     LoadPolicy;
};

struct TpLoadStatistic {      // The load statistic record at given timestamp.
    TpServiceID   ServiceID;
    TpFloat       LoadValue;      // Expressed in percentage.
    TpLoadLevel   LoadLevel;
    TpDateAndTime TimeStamp;
};

typedef sequence <TpLoadStatistic> TpLoadStatisticList;

enum TpLoadStatusError {      // The error code for getting the load status.
    LOAD_STATUS_ERROR_UNDEFINED, // Undefined error.
    LOAD_STATUS_ERROR_UNAVAILABLE // Unable to get the load status.
};

struct TpLoadStatisticError {      // The error for getting the load status at given timestamp.
    TpServiceID   ServiceID;
    TpFloat       LoadStatusError;
    TpDateAndTime TimeStamp;
};

typedef sequence <TpLoadStatisticError> TpLoadStatisticErrorList;

/*****************
//               Interface definitions
/*****************/

/* The Heartbeat Framework interface is used by the client application to supervise the
Framework or a SCF. */

interface IpHeartBeat : IpOsa {

    /* This method is invoked by the client application to make the service or Framework
supervision. */
    void send (
        in TpSessionID session      // The heartbeat session.
    );
}

```

```
    ) raises (TpGeneralException);

};

/* The Heartbeat client application interface is used by the Framework to supervise the client
application. */

interface IpAppHeartBeat : IpOsa {

    /* This method is invoked by the Framework to make the client application supervision. */
    void send (
        in TpSessionID session           // The heartbeat session.
    ) raises (TpGeneralException);

};

/* The Heartbeat Management Framework interface is used by the client application to
initialise a heartbeat supervision of the client application. */

interface IpHeartBeatMgmt : IpOsa {

    /* This method is invoked by the client application to register at the Framework for
heartbeat supervision. */
    void enableHeartBeat (
        in TpDuration duration,          // Duration in milliseconds between heartbeats.
        in IpAppHeartBeat appInterface,   // The callback interface the heartbeat is calling.
        out TpSessionID session          // The heartbeat session.
    ) raises (TpGeneralException);

    /* This method is invoked by the client application to stop its heartbeat supervision. */
    void disableHeartBeat (
        in TpSessionID session           // The heartbeat session.
    ) raises (TpGeneralException);

    /* This method is invoked by the client application to change the heartbeat period. */
    void changeTimePeriod (
        in TpDuration duration,          // Duration in milliseconds between heartbeats.
        in TpSessionID session           // The heartbeat session.
    ) raises (TpGeneralException);
}
```

```

};

/* The Heartbeat Management client application interface is used by the Framework to
initialise its heartbeat supervision of the Framework. */
interface IpAppHeartBeatMgmt : IpOsa {

    /* This method is invoked by the Framework to register at the client application for its
heartbeat supervision. */
    void enableAppHeartBeat (
        in TpDuration duration,           // Time interval in milliseconds between the heartbeats.
        in IpHeartBeat fwInterface,      // The callback interface the heartbeat is calling.
        in TpSessionID session          // The heartbeat session.
    ) raises (TpGeneralException);

    /* This method is invoked by the Framework to stop the heartbeat supervision by the
application. */
    void disableAppHeartBeat (
        in TpSessionID session           // The heartbeat session.
    ) raises (TpGeneralException);

    /* This method is invoked by the Framework to change the heartbeat period. */
    void changeTimePeriod (
        in TpDuration duration,           // Interval in milliseconds between the heartbeats.
        in TpSessionID session          // The heartbeat session.
    ) raises (TpGeneralException);

};

/* The Load Manager Framework interface is used by the client application for load balancing
management. */
interface IpLoadManager : IpOsa {

    /* This method is invoked by the client application to notify framework its current load
level (0,1, or 2) when the load level on the application has changed. */
    void reportLoad (
        in TpClientAppID requester,      // The identifier of the client application for
                                         // callbacks from the load balancing SCF.
    )
}

```

```

    in TpLoadLevel loadLevel          // The application's load level.
) raises (TpGeneralException);

/* This method is invoked by the client application to request load statistic records for
the framework and specified SCFs. */
void queryLoadReq (
    in TpClientAppID requester,      // The identifier of the client application for
                                    // callbacks from the load balancing SCF.
    in TpServiceIDList serviceIDs,   // Specifies the framework and SCFs for which the
                                    // load statistics shall be reported.
    in TpTimeInterval timeInterval   // The time interval within which the load statistics
                                    // are generated.
) raises (TpGeneralException);

/* This method is invoked by the client application to report load statistics back to the
framework that requested the information. */
void queryAppLoadRes (
    in TpLoadStatisticList loadStatistics // The application's load statistics.
) raises (TpGeneralException);

/* This method is invoked by the client application to return an error response to the
framework that requested the application's load statistics information. */
void queryAppLoadErr (
    in TpLoadStatisticErrorList loadStatisticsError // The error code associated with the
                                                    // failed attempt to retrieve the
                                                    // application's load statistics.
) raises (TpGeneralException);

/* This method is invoked by the client application to register the client application for
load management under various load conditions. */
void registerLoadController (
    in TpClientAppID requester,        // Identifies the client application for callbacks
                                    // from the load balancing SCF.
    in TpServiceIDList serviceIDs,    // Specifies the framework and SCFs to be
                                    // registered for load control.
) raises (TpGeneralException);

/* This method is invoked by the client application to unregister for load management. */
void unregisterLoadController (
    in TpClientAppID requester,        // Identifies the client application for callbacks from

```

```

                                // the load balancing SCF.

in TpServiceIDList serviceIDs      // Specifies the framework or SCFs to be
                                    // unregistered for load control.

) raises (TpGeneralException);

/* This method is invoked by the client application to resume load management notifications
to it from the framework and specified SCFs. */

void resumeNotification (
    in TpServiceIDList serviceIDs      // Specifies the framework and SCFs for which
                                    // notifications are to be resumed.

) raises (TpGeneralException);

/* This method is invoked by the client application to suspend load management
notifications to it from the framework and specified SCFs, while it handles a temporary
load condition. */

void suspendNotification (
    in TpServiceIDList serviceIDs      // Specifies the framework and SCFs for which
                                    // notifications are to be suspended.

) raises (TpGeneralException);

};

/* The Load Manager client application interface is used by the Framework to access the
application load balancing SCF. */

interface IpAppLoadManager : IpOsa {

/* This method is invoked by the Framework to request for load statistic records produced
by a specified application. */

void queryAppLoadReq (
    in TpServiceIDList serviceIDs,      // Specifies the SCFs or application for which the
                                    // load statistics shall be reported.

    in TpTimeInterval timeInterval      // The time interval within which the load statistics
                                    // are generated.

) raises (TpGeneralException);

/* This method is invoked by the Framework to return load statistics to the application
which requested the information. */

void queryLoadRes (

```

```
    in TpLoadStatisticList loadStatistics          // The load statistics supplied by the
                                                // Framework.

) raises (TpGeneralException);

/* This method is invoked by the Framework to return an error code to the application that
requested load statistics. */

void queryLoadErr (

in TpLoadStatisticErrorList loadStatisticsError      // The error code supplied by the
                                                       // Framework.

) raises (TpGeneralException);

/* This method is invoked by the Framework to disable load control activity at the client
application based on policy, after the load level of the Framework or SCF which has
been registered for load control moves back to normal. */

void disableLoadControl (

in TpServiceIDList serviceIDs          // Specifies the framework and SCFs for which the
                                         // load has changed to normal.

) raises (TpGeneralException);

/* This method is invoked by the Framework to enable load management activity at the client
application based on the policy, upon detecting load condition change. */

void enableLoadControl (

in TpLoadStatisticList loadStatistics          // The new load statistics.

) raises (TpGeneralException);

/* This method is invoked by the Framework to resume the notification from an application
for its load status after the detection of load level change at the Framework and the
evaluation of the load balancing policy. */

void resumeNotification() raises (TpGeneralException);

/* This method is invoked by the Framework to suspend the notification from an application
for its load status after the detection of load level change at the Framework and the
evaluation of the load balancing policy. */

void suspendNotification() raises (TpGeneralException);

};

/* The Fault Manager Framework interface is used by the client application to inform the
```

```

Framework of events that affect the integrity of the Framework and SCFs, and to request
information about the integrity of the system. */

interface IpFaultManager : IpOsa {

    /* This method may be invoked by the client application to test that the Framework or a
    SCF is operational. */
    void activityTestReq (
        in TpActivityTestId activityTestId,           // Identifier provided by the client
                                                    // application to correlate the
                                                    // response with this request.
        in TpServiceID svcID,                      // Identifies for which SCF the client
                                                    // application is requesting the activity test
                                                    // to be done.
        in TpClientAppID appID                     // Identifies which client application is
                                                    // requesting the activity test (and therefore
                                                    // which application receives the results).
    ) raises (TpGeneralException);

    /* This method is invoked by the client application to return the result of a previously
    requested activity test. */
    void appActivityTestRes (
        in TpActivityTestId activityTestId,           // Used by the Framework to correlate this
                                                    // response with the original request.
        in TpActivityTestRes activityTestResult      // Result of the activity test.
    ) raises (TpGeneralException);

    /* This method is invoked by the client application to inform the Framework that it can no
    longer use the indicated SCF. */
    void svcUnavailableInd (
        in TpServiceID serviceID,                  // Identity of the SCF which can no longer be used.
        in TpClientAppID appID                    // Identity of the application sending the indication.
    ) raises (TpGeneralException);

    /* This method is invoked by the client application to request fault statistics from the
    Framework. */
    void genFaultStatsRecordReq (
        in TpTimeInterval timePeriod,             // The period over which the fault statistics
                                                // are to be generated.
        in TpServiceIDList serviceIDList,         // The SCFs that the application would like
                                                // to have included in the general fault
    ) raises (TpGeneralException);
}

```

```

                // statistics record.

in TpClientAppID appID           // Identifies which client application is
                                 // requesting the statistics record (and
                                 // therefore should receive it).

) raises (TpGeneralException);

};

/* The Fault Manager client application interface is used by the Framework to inform the
application of events that affect the integrity of the Framework, SCF or client
application. */

interface IpAppFaultManager : IpOsa {

    /* This method is invoked by the Framework, in response to an activityTestReq, to return
the result of the activity test in this method. */
void activityTestRes (
    in TpActivityTestId activityTestId,          // The identifier provided to correlate this
                                                // response with the original request.

    in TpActivityTestRes activityTestResult      // Result of the activity test.

) raises (TpGeneralException);

/* This method is invoked by the Framework to request that the client application carries
out an activity test to check that is it operating correctly. */
void appActivityTestReq (
    in TpActivityTestId activityTestId          // The identifier provided to correlate this
                                                // response with the original request.

) raises (TpGeneralException);

/* This method is invoked by the Framework to notify the client application of a failure
within the Framework. */
void fwFaultReportInd (
    in TpInterfaceFault fault                  // The fault that has been detected.

) raises (TpGeneralException);

/* This method is invoked by the Framework to notify the client application that a
previously reported fault has been rectified. */
void fwFaultRecoveryInd (
    in TpInterfaceFault fault                 // The fault from which the framework has recovered.

```

```

) raises (TpGeneralException);

/* This method is invoked by the Framework to inform the client application that it can no
longer use the indicated SCF due to a failure. */
void svcUnavailableInd (
    in TpServiceID serviceID,           // Identity of the SCF which can no longer be used.
    in TpSvcUnavailReason reason       // The reason why the SCF is no longer available.
) raises (TpGeneralException);

/* This method is invoked by the Framework to provide fault statistics to a client
application in response to a genFaultStatsRecordReq. */

void genFaultStatsRecordRes (
    in TpFaultStatsRecord faultStatistics,      // The fault statistics record.
    in TpServiceIDList serviceIDs             // The SCFs that have been included in the
                                              // general fault statistics record.
) raises (TpGeneralException);

};

/* The OAM Framework interface is used by the client application to query the system date and
time, for synchronisation purposes. */
interface IpOAM : IpOsa {

/* This method is invoked by the client application to interchange the system an client
application date and time. */
void systemDateTimeQuery (
    in TpDateAndTime clientDateAndTime,        // The date and time of the client.
    out TpDateAndTime systemDateAndTime        // The date and time of the system.
) raises (TpGeneralException);

};

/* The OAM client application interface is used by the Framework to query the application date
and time, for synchronisation purposes. */
interface IpAppOAM : IpOsa {

```

```

/* This method is invoked by the Framework to interchange the system an client application
date and time. */

void systemDateTimeQuery (
    in TpDateAndTime systemDateTime,           // The date and time of the system.
    out TpDateAndTime clientDateTime          // The date and time of the client.
) raises (TpGeneralException);

};

} ; } ; } ; } ; }


```

## 9.2.4 Registration IDL

```

#include <fw.idl>

module org{
module threegpp{
module osa{
module fw{
module registration{



/*****                                                 *****/
//                                         Interface definitions // 
/*****                                                 *****/

/* The Service Registration Framework interface provides the methods used for the registration
of network SCFs at the Framework. */

interface IpServiceRegistration : IpOsa {

    /* This method is used to register a SCF in the Framework, for subsequent discovery by
the applications. */
    void registerService (
        in TpServiceTypeName      serviceTypeName,
        in TpServicePropertyList   servicePropertyList,
        out TpServiceID            serviceID
    ) raises (TpGeneralException);

    /* This method informs the Framework of the availability of a service factory for a
previously registered SCF. */

```

## 9.3 Call Control

### 9.3.1 Common Data Types for Call Control

```
// source file: CC.idl
// Generic Call Data description

#ifndef __OSA_CC_DEFINED
#define __OSA_CC_DEFINED

#include <OSA.idl>

module org
{
```

```

module threegpp
{
    module osa
    {
        module cc
        {
            /* Defines the mechanism that will be used to alert a called party. */
            typedef TpInt32TpCallAlertingMechanism;

            /* Defines the bearer service associated with the call. */
            enum TpCallBearerService
            {
                P_CALL_BEARER_SERVICE_UNKNOWN,                                /* Bearer capability information
                                                                           unknown at this time*/
                P_CALL_BEARER_SERVICE_SPEECH,                                 /* Speech*/
                P_CALL_BEARER_SERVICE_DIGITALUNRESTRICTED,                 /* Unrestricted digital information*/
                P_CALL_BEARER_SERVICE_DIGITALRESTRICTED,                   /* Restricted digital information*/
                P_CALL_BEARER_SERVICE_AUDIO,                                  /* 3.1 kHz audio*/
                P_CALL_BEARER_SERVICE_DIGITALUNRESTRICTEDTONES,           /* Unrestricted digital information
                                                                           with tones/announcements*/
                P_CALL_BEARER_SERVICE_VIDEO,                                /* Video*/
            };
        }

        /*This data defines the bearer capabilities associated with the call. (3G TS 24.002) This
         information is network operator specific and may not always be available because there
         is no standard protocol to retrieve the information */
        enum TpCallNetworkAccessType
        {
            P_CALL_NETWORK_ACCESS_TYPE_UNKNOWN,      /* Network type information unknown at this time
                                                       */
            P_CALL_NETWORK_ACCESS_TYPE_POT,          /* POTS */
            P_CALL_NETWORK_ACCESS_TYPE_ISDN,         /* ISDN */
            P_CALL_NETWORK_ACCESS_TYPE_DIALUPINTERNET, /* Dial-up Internet */
            P_CALL_NETWORK_ACCESS_TYPE_XDSL,          /* xDSL */
            P_CALL_NETWORK_ACCESS_TYPE_WIRELESS,       /* Wireless */
        };

        /* Defines the category of a calling or called party (e.g. call priority, payphone,
         prepaid).*/
        enum TpCallPartyCategory
        {
            P_CALL_PARTY_CATEGORY_UNKNOWN,           /*calling party's category unknown at this time*/
            P_CALL_PARTY_CATEGORY_OPERATOR_F,        /* operator, language French*/
            P_CALL_PARTY_CATEGORY_OPERATOR_E,        /* operator, language English*/
            P_CALL_PARTY_CATEGORY_OPERATOR_G,        /* operator, language German*/
            P_CALL_PARTY_CATEGORY_OPERATOR_R,        /* operator, language Russian*/
            P_CALL_PARTY_CATEGORY_OPERATOR_S,        /* operator, language Spanish*/
            P_CALL_PARTY_CATEGORY_ORDINARY_SUB,      /* ordinary calling subscriber*/
            P_CALL_PARTY_CATEGORY_PRIORITY_SUB,     /* calling subscriber with priority*/
            P_CALL_PARTY_CATEGORY_DATA_CALL,         /* data call (voice band data) */
            P_CALL_PARTY_CATEGORY_TEST_CALL,         /* test call*/
            P_CALL_PARTY_CATEGORY_PAYPHONE,          /* payphone*/
        };

        /* This data type defines the tele-service associated with the call. (Q.763: User
         Teleservice Information, Q.931: High Layer Compatibility Information, and 3G TS
         22.003)Defines the tele-service associated with the call (e.g. speech, video, fax, file
         transfer, browsing). */
        enum TpCallTeleService
        {
            P_CALL_TELE_SERVICE_UNKNOWN,           /* Teleservice information unknown at this time*/
            P_CALL_TELE_SERVICE_TELEPHONY,         /* Telephony */
            P_CALL_TELE_SERVICE_FAX_2_3,           /* Facsimile Group 2/3 */
            P_CALL_TELE_SERVICE_FAX_4_I,           /* Facsimile Group 4, Class I */
            P_CALL_TELE_SERVICE_FAX_4_II_III,      /* Facsimile Group 4, Classes II and III */
            P_CALL_TELE_SERVICE_VIDEOTEX_SYN,      /* Syntax based Videotex */
            P_CALL_TELE_SERVICE_VIDEOTEX_INT,      /* International Videotex interworking via gateways
or interworking units */
            P_CALL_TELE_SERVICE_TELEX,             /* Telex service*/
            P_CALL_TELE_SERVICE_MHS,               /* Message Handling Systems */
            P_CALL_TELE_SERVICE_OSI,               /* OSI application*/
            P_CALL_TELE_SERVICE_FTAM,              /* FTAM application*/
            P_CALL_TELE_SERVICE_VIDEO,             /* Videotelephony*/
            P_CALL_TELE_SERVICE_VIDEO_CONF,        /* Videoconferencing*/
            P_CALL_TELE_SERVICE_AUDIOGRAPH_CONF,   /* Audiographic conferencing*/
            P_CALL_TELE_SERVICE_MULTIMEDIA,        /* Multimedia services*/
        };
    }
}

```

```

P_CALL_TELE_SERVICE_CS_INI_H221,      /* Capability set of initial channel of H.221*/
P_CALL_TELE_SERVICE_CS_SUB_H221,      /* Capability set of subsequent channel of H.221*/
P_CALL_TELE_SERVICE_CS_INI_CALL,      /* Capability set of initial channel associated with
an active 3.1 kHz audio or speech call.*/
P_CALL_TELE_SERVICE_DATATRAFFIC,     /* Data traffic.*/
P_CALL_TELE_SERVICE_EMERGENCY_CALLS,  /* Emergency Calls*/
P_CALL_TELE_SERVICE_SMS_MT_PP,       /* Short message MT/PP*/
P_CALL_TELE_SERVICE_SMS_MO_PP,       /* Short message MO/PP*/
P_CALL_TELE_SERVICE_CELL_BROADCAST,  /* Cell Broadcast Service*/
P_CALL_TELE_SERVICE_ALT_SPEECH_FAX_3,/* Alternate speech and facsimile group 3*/
P_CALL_TELE_SERVICE_AUTOMATIC_FAX_3,/* Automatic Facsimile group 3*/
P_CALL_TELE_SERVICE_VOICE_GROUP_CALL,/* Voice Group Call Service*/
P_CALL_TELE_SERVICE_VOICE_BROADCAST /* Voice Broadcast Service*/
};

/* Defines a specific call event report type. */
enum TpCallAppInfoType
{
    P_CALL_APP_UNDEFINED,           /* Undefined */
    P_CALL_APP_ALERTING_MECHANISM, /* The alerting mechanism or pattern to use */
    P_CALL_APP_NETWORK_ACCESS_TYPE, /* The network access type (e.g. ISDN) */
    P_CALL_APP_TELE_SERVICE,        /* Indicates the tele-service (e.g. speech) and
related info such as clearing programme */
    P_CALL_APP_BEARER_SERVICE,      /* Indicates the bearer service (e.g. 64kb/s
unrestricted data). */
    P_CALL_APP_PARTY_CATEGORY,      /* The category of the calling or called party */
    P_CALL_APP_PRESENTATION_ADDRESS,/* The address to be presented to other call parties
*/
    P_CALL_APP_GENERIC_INFO,        /* Carries unspecified application-SCF information
*/
    P_CALL_APP_ADDITIONAL_ADDRESS,  /* Indicates an additional address */
};

/* Defines the Tagged Choice of Data Elements that specify call application-related
specific information. */
union TpCallAppInfo switch(TpCallAppInfoType)
{
    case P_CALL_APP_TELE_SERVICE:
        TpCallTeleService CallAppTeleService;
    case P_CALL_APP_BEARER_SERVICE:
        TpCallBearerService CallAppBearerService;
    case P_CALL_APP_PARTY_CATEGORY:
        TpCallPartyCategory CallAppPartyCategory;
    case P_CALL_APP_PRESENTATION_ADDRESS:
        TpAddress CallAppPresentationAddress;
    case P_CALL_APP_GENERIC_INFO:
        TpString CallAppGenericInfo;
    case P_CALL_APP_ADDITIONAL_ADDRESS:
        TpAddress CallAppAdditionalAddress;
    case P_CALL_APP_ALERTING_MECHANISM:
        TpCallAlertingMechanism CallAppAlertingMechanism;
    case P_CALL_APP_NETWORK_ACCESS_TYPE:
        TpCallNetworkAccessType CallAppNetworkAccessType;
};

typedef sequence <TpCallAppInfo> TpCallAppInfoSet;

enum TpCallChargeOrderCategory
{
    P_CALL_CHARGE_PER_TIME, /* Charge per time*/
    P_CALL_CHARGE_NETWORK /* Operator specific charge plan specification, e.g. charging
table name / charging table entry*/
};

/* Defines the Tagged Choice of Data Elements that specify the charge plan for the call. */
union TpCallChargeOrder switch(TpCallChargeOrderCategory)
{
    case P_CALL_CHARGE_PER_TIME: TpChargePerTime ChargePerTime;
    case P_CALL_CHARGE_NETWORK: TpString NetworkCharge;
};

/* Defines the Sequence of Data Elements that specify the charge plan for the call This
data type is identical to a TpString, and defines the call charge plan to be used for the
call. The values of this data type are operator specific. */

```

```

struct TpCallChargePlan
{
    TpCallChargeOrder ChargeOrderType;
    TpString Currency;
    TpString AdditionalInfo;
};

const TpInt32 P_EVENT_NAME_UNDEFINED = 0;                                // Undefined
const TpInt32 P_EVENT_GCCS_OFFHOOK_EVENT = 1;                            // Offhook event
const TpInt32 P_EVENT_GCCS_ADDRESS_COLLECTED_EVENT = 2;                  // Address information
collected
    const TpInt32 P_EVENT_GCCS_ADDRESS_ANALYSED_EVENT = 4;                // Address information is
analysed
    const TpInt32 P_EVENT_GCCS_CALLED_PARTY_BUSY = 8;                      // Called party is busy
    const TpInt32 P_EVENT_GCCS_CALLED_PARTY_UNREACHABLE = 16;               // Called party is
unreachable
    const TpInt32 P_EVENT_GCCS_NO_ANSWER_FROM_CALLED_PARTY = 32;            // No answer from called
party
    const TpInt32 P_EVENT_GCCS_ROUTE_SELECT_FAILURE = 64;                   // Failure in routing the
call
    const TpInt32 P_EVENT_GCCS_ANSWER_FROM_CALL_PARTY = 128;                // Party answered call

typedef TpInt32 TpCallEventName; /*Defines the names of event being notified. */

enum TpCallNotificationType
{
    P_ORIGINATING, // The notification is related to the originating user in the call.
    P_TERMINATING // The notification is related to the terminating user in the call.
};

struct TpCallEventCriteria
{
    TpAddressRange DestinationAddress;           /*Destination address or address range*/
    TpAddressRange OriginationAddress;          /*Origination address or address range */
    TpCallEventName CallEventName;              /*Name of the event(s) */
    TpCallNotificationType CallNotificationType; /*Indicates whether the criteria are
related to the originating or terminating user in the call */
};

/* Defines a sequence of data elements that specify a requested call event notification
criteria with the associated assignmentID */
struct TpCallEventCriteriaResult
{
    TpCallEventCriteria EventCriteria;
    TpInt32 AssignmentID;
};

/* Defines a set of TpCallEventCriteriaResult */
typedef sequence <TpCallEventCriteriaResult> TpCallEventCriteriaResultSet;

//Defines the type of notification.
//Indicates whether it is related to the originating or the terminating user in the call.
struct TpCallEventInfo
{
    TpAddress DestinationAddress;
    TpAddress OriginatingAddress;
    TpAddress OriginalDestinationAddress;
    TpAddress RedirectingAddress;
    TpCallAppInfoSet CallAppInfo;
    TpCallEventName CallEventName;
    TpCallNotificationType CallNotificationType;
};

/* Defines the Sequence of Data Elements that specify the cause of the release of a call.*/
struct TpCallReleaseCause {
TpInt32 Value;
TpInt32 Location;
};

/* Defines the Sequence of Data Elements that specify the reason for the call ending.*/
struct TpCallEndedReport
{
    TpSessionID CallLegSessionID;
    TpCallReleaseCause Cause;
};

/* Defines a specific call error. */

```

```

enum TpCallErrorType
{
    P_CALL_ERROR_UNDEFINED,          /* Undefined */
    P_CALL_ERROR_INVALID_ADDRESS,   /* The operation failed because an invalid address was
given */
    P_CALL_ERROR_INVALID_STATE     /* The call was not in a valid state for the requested
operation */
};

/* Defines the Tagged Choice of Data Elements that specify additional call error and call
error specific information. This is also used to specify call leg errors and call information
errors. */
union TpCallAdditionalErrorInfo switch(TpCallErrorType)
{
    case P_CALL_ERROR_INVALID_ADDRESS: TpAddressError CallErrorInvalidAddress;
    default: short Dummy; // allows initialisation of the union in the default case
};

/* Defines the Sequence of Data Elements that specify the additional information relating
to an undefined call error. */
struct TpCallError
{
    TpCallAdditionalErrorInfo AdditionalErrorInfo;
    TpCallErrorType ErrorType;
    TpDateAndTime ErrorTime;
};

/* Defines the cause of the call fault detected. */
enum TpCallFault
{
    P_CALL_FAULT_UNDEFINED,        /* Undefined */

    P_CALL_TIMEOUT_ON_RELEASE,    /* Final report has been sent to the application, but the
application did not explicitly release or deassign the call object, within a specified time.
*/
    P_CALL_TIMEOUT_ON_INTERRUPT /* Application did not instruct the gateway how to handle
the call within a specified time, after the gateway reported an event that was requested by
the application in interrupt mode.*/
};

/* Defines the type of call information requested and reported */
const TpInt32 P_CALL_INFO_UNDEFINED = 0;           /* Undefined */
const TpInt32 P_CALL_INFO_TIMES = 1;                /* Relevant call times */
const TpInt32 P_CALL_INFO_RELEASE_CAUSE = 2;        /* Call release cause. */
const TpInt32 P_CALL_INFO_INTERMEDIATE = 4;         /* Send only intermediate reports (i.e.,
when a party leaves the call). */

typedef TpInt32 TpCallInfoType;

/* Defines the Sequence of Data Elements that specify the call information requested.
Information that was not requested may be undefined or not present. */
struct TpCallInfoReport
{
    TpCallInfoType CallInfoType;
    TpDateAndTime CallInitiationStartTime;
    TpDateAndTime CallConnectedToResourceTime;
    TpDateAndTime CallConnectedToDestinationTime;
    TpDateAndTime CallEndTime;
    TpCallReleaseCause Cause;
};

/* Defines the mode that the call will monitor for events, or the mode that the call is in
following a detected event. */
enum TpCallMonitorMode
{
    P_CALL_MONITOR_MODE_INTERRUPT,      /* The call event is intercepted by the call control
SCF and call processing is interrupted. The application is notified of the event and call
processing resumes following an appropriate API call or network event (such as a call
release) */
    P_CALL_MONITOR_MODE_NOTIFY,        /* The call event is detected by the call control SCF
but not intercepted. The application is notified of the event and call processing continues
*/
    P_CALL_MONITOR_MODE_DO_NOT_MONITOR /* Do not monitor for the event */
};

/* Defines the type of call overload that has been detected (and possibly acted upon) by
the network. */
enum TpCallOverloadType

```

```

{
    P_CALL_OVERLOAD_TYPE_UNDEFINED,      /* Infinite interval (do not admit any calls) */
    P_CALL_OVERLOAD_TYPE_NEW_CALLS,     /* New calls to the application are causing overload
(i.e. inbound overload) */
    P_CALL_OVERLOAD_TYPE_ROUTED_CALLS /* Calls being routed to destination or origination
addresses by the application are causing overload (i.e. outbound overload) */
};

/* Defines a specific call event report type. */
enum TpCallReportType
{
    P_CALL_REPORT_UNDEFINED,           /* Undefined */
    P_CALL_REPORT_PROGRESS,           /* Call routing progress event */
    P_CALL_REPORT_ALERTING,           /* Call alerting at address */
    P_CALL_REPORT_ANSWER,             /* Call answered at address */
    P_CALL_REPORT_BUSY,               /* Called address refused call due to busy */
    P_CALL_REPORT_NO_ANSWER,          /* No answer at called address */
    P_CALL_REPORT_DISCONNECT,         /* Call disconnect requested by address */
    P_CALL_REPORT_REDIRECTED,
    P_CALL_REPORT_SERVICE_CODE,
    P_CALL_REPORT_ROUTING_FAILURE
};

/* Defines the Tagged Choice of Data Elements that specify additional call report
information. */
union TpCallAdditionalReportInfo switch(TpCallReportType)
{
    case P_CALL_REPORT_BUSY: TpCallReleaseCause RefuseBusy;
    case P_CALL_REPORT_DISCONNECT: TpCallReleaseCause CallDisconnect;
    case P_CALL_REPORT_REDIRECTED: TpAddress ForwardAddress;
    case P_CALL_REPORT_SERVICE_CODE: TpCallReleaseCause ServiceCode;
    case P_CALL_REPORT_ROUTING_FAILURE: TpCallReleaseCause RoutingFailure;

    default: short Dummy; // allows initialisation of the union in the default case
};

struct TpCallReport
{
    TpCallMonitorMode MonitorMode;
    TpDateAndTime CallEventTime;
    TpCallReportType CallReportType;
    TpCallAdditionalReportInfo AdditionalReportInfo;
};

/* Defines the different types of service codes that can be received during the call.*/
enum TpCallServiceCodeType
{
    P_CALL_SERVICE_CODE_UNDEFINED, /* The type of service code is unknown. The
corresponding string is operator specific.*/
    P_CALL_SERVICE_CODE_DIGITS,   /* The user entered a digit sequence during the call. The
corresponding string is an ascii representation of the received digits. */
    P_CALL_SERVICE_CODE_FACILITY, /* A facility information element is received. The
corresponding string contains the facility information element as defined in ITU Q.932*/
    P_CALL_SERVICE_CODE_U2U,      /* A user-to-user message was received. The associated string
contains the content of the user-to-user information element. */
    P_CALL_SERVICE_CODE_HOOKFLASH, /* The user performed a hookflash, optionally followed
by some digits. The corresponding string is an ascii representation of the entered digits. */
    P_CALL_SERVICE_CODE_RECALL /* The user pressed the register recall button, optionally
followed by some digits. The corresponding string is an ascii representation of the entered
digits. */
};

/* Defines the Sequence of Data Elements that specify the service code and type of service
code received during a call. The service code type defines how the value string should be
interpreted. Defines the service code received during a call. For example, this may be a
digit sequence, user-user information, recall, flash-hook or ISDN Facility Information
Element. This data type is identical to a TpString. The coding of this data type is operator
specific. */
struct TpCallServiceCode
{
    TpCallServiceCodeType CallServiceCodeType;
    TpString ServiceCodeValue;
};

/* Defines the Tagged Choice of Data Elements that specify specific criteria. */
union TpCallAdditionalReportCriteria switch(TpCallReportType)

```

```

{
    case P_CALL_REPORT_NO_ANSWER: TpDuration NoAnswerDuration;
    case P_CALL_REPORT_SERVICE_CODE: TpCallServiceCode ServiceCode;
    default: short Dummy; // allows initialisation of the union in the default case
};

/* Defines the Sequence of Data Elements that specify the criteria relating to call report
requests. */
struct TpCallReportRequest
{
    TpCallMonitorMode MonitorMode;
    TpCallReportType CallReportType;
    TpCallAdditionalReportCriteria AdditionalReportCriteria;
};

/* Defines a Numbered Set of Data Elements of TpCallReportRequest. */
typedef sequence <TpCallReportRequest> TpCallReportRequestSet;

const TpInt32 P_CALL_SUPERVISE_TIMEOUT = 1; /* The call supervision timer has expired.
*/
const TpInt32 P_CALL_SUPERVISE_CALL_ENDED = 2; /* The call has ended, either due to timer
expiry or calling or called party release. In case the called party disconnects but a follow-
on call can still be made also this indication is used.*/
const TpInt32 P_CALL_SUPERVISE_TONE_APPLIED = 4; /* A warning tone has been applied. */
const TpInt32 P_CALL_SUPERVISE_UI_FINISHED = 8; /* The user interaction has finished */

/* Defines the responses from the call control SCF for calls that are supervised:*/
typedef TpInt32 TpCallSuperviseReport;

const TpInt32 P_CALL_SUPERVISE_RELEASE = 1; /* Release the call when the call
supervision timer expires. */
const TpInt32 P_CALL_SUPERVISE_RESPOND = 2; /* Notify the application when the call
supervision timer expires. */
const TpInt32 P_CALL_SUPERVISE_APPLY_TONE = 4; /* Send a warning tone to the controlling
party when the call supervision timer expires. If call release is requested, then the call
will be released following the tone after an administered time period */

/* Defines the following treatment of the call by the call control SCF when the call
supervision timer expires.*/
typedef TpInt32 TpCallSuperviseTreatment;

/* Define the possible Exceptions. */
const TpInt32 P_GCCS_SERVICE_INFORMATION_MISSING = 256;
const TpInt32 P_GCCS_SERVICE_FAULT_ENCOUNTERED = 257;
const TpInt32 P_GCCS_UNEXPECTED_SEQUENCE = 258;
const TpInt32 P_GCCS_INVALID_ADDRESS = 259;
const TpInt32 P_GCCS_INVALID_CRITERIA = 261;
const TpInt32 P_GCCS_INVALID_NETWORK_STATE = 262;

exception TpGCCSEException
{
    TpInt32 exceptionType;
};

}; // end module cc
}; // end module osa
}; // end module threegpp
}; // end module org

#endif

// END file CC.idl

```

### 9.3.2 Generic Call Control IDL

```

// source file: GCC.idl
// GenericCall Interface description

#ifndef __OSA_CC_GCC_DEFINED
#define __OSA_CC_GCC_DEFINED

#include <CC.idl>

module org {
    module threegpp {

```

```

module osa {
  module cc {
    module gcc {

interface IpAppCallControlManager; // forward definition
interface IpAppCall; // forward definition

/* This interface is the SCF manager' interface for Generic Call Control. */
interface IpCallControlManager : IpService {
  /* This method is used to enable call notifications. */
  void enableCallNotification (
    in IpAppCallControlManager appInterface,
    in TpCallEventCriteria eventCriteria,
    out TpAssignmentID assignmentID
  )
  raises (TpGCCSEException, TpGeneralException);

  /* This method is used by the application to disable call notifications.*/
  void disableCallNotification (
    in TpAssignmentID assignmentID
  )
  raises (TpGCCSEException, TpGeneralException);

  void changeCallNotification (
    in TpAssignmentID assignmentID,
    in TpCallEventCriteria eventCriteria
  )
  raises (TpGCCSEException, TpGeneralException);

  void getCriteria (
    out TpCallEventCriteriaResultSet eventCriteria
  )
  raises (TpGCCSEException, TpGeneralException);
};

/* This interface provides the means to control a simple call. */
interface IpCall : IpService {
  /* This method requests routing of the call to the destination party.*/
  void routeReq (
    in TpSessionID callSessionID,
    in TpCallReportRequestSet responseRequested,
    in TpAddress targetAddress,
    in TpAddress originatingAddress,
    in TpAddress originalDestinationAddress,
    in TpAddress redirectingAddress,
    in TpCallAppInfoSet appInfo,
    out TpSessionID callLegSessionID
  )
  raises (TpGCCSEException, TpGeneralException);

  /* This method requests the release of the call and associated objects.*/
  void release (
    in TpSessionID callSessionID,
    in TpCallReleaseCause cause
  )
  raises (TpGCCSEException, TpGeneralException);

  /* This method requests that the relationship between the application and
   the call and associated objects be de-assigned. */
  void deassignCall (
    in TpSessionID callSessionID
  )
  raises (TpGCCSEException, TpGeneralException);

  /* This method requests information associated with the call.*/
  void getCallInfoReq (
    in TpSessionID callSessionID,
    in TpCallInfoType callInfoRequested
  )
  raises (TpGCCSEException, TpGeneralException);

  /* Set an operator specific charge plan for the call. */
  void setCallChargePlan (
    in TpSessionID callSessionID,
    in TpCallChargePlan callChargePlan
  )
}

```

```

    raises (TpGCCSEception, TpGeneralException);

/* The application calls this method to supervise a call. */
void superviseCallReq (
    in TpSessionID callSessionID,
    in TpDuration time,
    in TpCallSuperviseTreatment treatment

)
raises (TpGCCSEception, TpGeneralException);

void setAdviceOfCharge(
    in TpSessionID callSessionID,
    in TpAoCInfo aOCInfo,
    in TpDuration tariffSwitch
)
raises (TpGCCSEception, TpGeneralException);
};

/* Sequence of Data Elements that unambiguously specify the Generic Call object */
struct TpCallIdentifier {
    IpCall CallReference;
    TpSessionID CallSessionID;
};

/* The generic call control manager application interface provides the
application call control management functions to the generic call control
SCF. */
interface IpAppCallControlManager : IpOsa {
    void callAborted (
        in TpSessionID callReference
    )
    raises (TpGCCSEception, TpGeneralException);

    /* This method notifies the application of the arrival of a call-related event. */
    void callEventNotify (
        in TpCallIdentifier callReference,
        in TpCallEventInfo eventInfo,
        in TpAssignmentID assignmentID,
        out IpAppCall appInterface
    )
    raises (TpGCCSEception, TpGeneralException);

    /* This method indicates to the application that all event notifications
have been terminated.*/
    void callNotificationInterrupted ()
    raises (TpGCCSEception, TpGeneralException);

    void callNotificationContinued ()
    raises (TpGCCSEception, TpGeneralException);
};

/* The application side of the simple call interface is used to handle call
request responses and state reports. */
interface IpAppCall : IpOsa {
    /* This method indicates that the request to route the call to the
destination was successful.*/
    void routeRes (
        in TpSessionID callSessionID,
        in TpCallReport eventReport,
        in TpSessionID callLegSessionID
    )
    raises (TpGCCSEception, TpGeneralException);

    /* This method indicates that the request to route the call to the
destination party was unsuccessful. */
    void routeErr (
        in TpSessionID callSessionID,
        in TpCallError errorIndication,
        in TpSessionID callLegSessionID
    )
    raises (TpGCCSEception, TpGeneralException);

    /* This method reports all necessary information requested by the
application, for example to calculate charging.*/
    void getCallInfoRes (
        in TpSessionID callSessionID,

```

### 9.3.3 Enhanced Call Control IDL

The IDL in this section is only supplied in order to make the User Interaction IDL compile.

With the `createUICall()` method on the `UIManager` object it is possible to associate the `UICall` object to a `Call` object as well as a `CallLeg` object. The `CallLeg` object is not used in this specification. However the IDL for this interface has to be supplied otherwise the User Interaction IDL will not compile.

```
// source file: ECC.idl

#ifndef __OSA_CC_ECC_DEFINED
#define __OSA_CC_ECC_DEFINED

#include <GCC.idl>

module org {
    module threeGPP {

```

```

module osa {
    module cc {
        module ecc {

            typedef TpInt32 TpMediaType;

            const TpInt32 P_AUDIO = 1;
            const TpInt32 P_VIDEO = 2;
            const TpInt32 P_DATA = 4;

            typedef TpInt32 TpAudioCapabilitiesType;
            typedef TpInt32 TpVideoCapabilitiesType;
            typedef TpInt32 TpDataCapabilities;

            union TpChannelDataTypeRequest switch(TpMediaType) {
                case P_DATA: TpDataCapabilities Data;
                case P_VIDEO: TpVideoCapabilitiesType Video;
                case P_AUDIO: TpAudioCapabilitiesType Audio;
            };

            typedef TpChannelDataTypeRequest TpChannelDataType;

            enum TpChannelDirection {
                P_INCOMING,
                P_OUTGOING
            };

            struct TpChannelRequest {
                TpChannelDataTypeRequest DataTypeRequest;
                TpChannelDirection Direction;
            };

            typedef sequence <TpChannelRequest> TpChannelRequestSet;

            enum TpCallLegType {
                P_CALL_LEG_TYPE_UNDEFINED,
                P_CALL_LEG_TYPE_CONTROLLING,
                P_CALL_LEG_TYPE_PASSIVE
            };

            enum TpCallLegInfoType {
                P_CALL_LEG_INFO_UNDEFINED,
                P_CALL_LEG_INFO_ADDRESS,
                P_CALL_LEG_INFO_RELEASE_CAUSE,
                P_CALL_LEG_INFO_APPINFO,
                P_CALL_LEG_INFO_TIMES
            };

            interface IpMMChannel : IpService {
                void close (
                    in TpSessionID channelSessionID
                )
                raises (TpGeneralException,TpGCCSEException);
            };

            struct TpChannel {
                TpChannelDirection Direction;
                IpMMChannel Channel;
                TpChannelDataType DataType;
                TpInt32 ChannelNumber;
            };

            typedef sequence <TpChannel> TpChannelSet;

            interface IpCallLeg : IpService {
                void routeCallLegToOrigination (
                    in TpSessionID callLegSessionID,
                    in TpAddress targetAddress,
                    in TpAddress originatingAddress,

```



```
#endif
// END file ECC.idl
```

## 9.4 User Interaction IDL

### 9.4.1 Common data types for User Interaction

```
// source file: UI.idl
// User Interaction data description

#ifndef __OSA_UI_DEFINED
#define __OSA_UI_DEFINED

#include <OSA.idl>

module org {
    module threegpp {
        module osa {
            module ui {

/* Defines the additional properties for the collection of information */
                struct TpUICollectCriteria {
                    TpInt32 MinLength;           /* minimum number of characters to collect */
                    TpInt32 MaxLength;          /* maximum number of characters to collect */
                    TpString EndSequence;       /* character(s) which terminate an input of variable length. */
                    TpDuration StartTimeout;    /* defines a duration (in seconds) */
                    TpDuration InterCharTimeout; /* value for the inter-character time-out timer. */
                };

/* Defines the UI call error codes. */
                enum TpUIError {
                    P_UI_ERROR_UNDEFINED,      /* Undefined error */
                    P_UI_ERROR_ILLEGAL_ID,    /* The information id specified is invalid */
                    P_UI_ERROR_ID_NOT_FOUND,   /* Information id is not known to the the User Interaction SCFs */
                    P_UI_ERROR_RESOURCE_UNAVAILABLE, /* Resources used by the User Interaction SCFs are unavailable.
                    */
                    P_UI_ERROR_ILLEGAL_RANGE,  /* The values for minimum and maximum collection length are out of range */
                    P_UI_ERROR_IMPROPER_CALLER_RESPONSE, /* Improper user response */
                    P_UI_ERROR_ABANDON,        /* Specified leg is disconnected before the send information completed */
                    P_UI_ERROR_NO_OPERATION_ACTIVE, /* No active user interaction for the specified leg. */
                    P_UI_ERROR_NO_SPACE_AVAILABLE /* There is no more storage capacity to record the message.*/
                };

/* Defines the type of the dataString parameter in the method userInteractionEventNotify */
                enum TpUIEventInfoDataType {
                    P_UI_EVENT_DATA_TYPE_UNDEFINED, /* Undefined */
                    P_UI_EVENT_DATA_TYPE_UNSPECIFIED, /* Unspecified data */
                    P_UI_EVENT_DATA_TYPE_TEXT,       /* Text */
                    P_UI_EVENT_DATA_TYPE_USSD_DATA /* USSD data starting with coding scheme */
                };

/* Defines the Sequence of Data Elements that specify the additional criteria for receiving a UI notification */
                struct TpUIEventCriteria {
                    TpAddressRange OriginatingAddress; /* Address of the end-user for which notification shall be handled */
                    TpAddressRange DestinationAddress;
                    TpString ServiceCode; /* 2 digit code indicating the UI to be triggered. */
                };

/* Defines the Sequence of Data Elements that specify a UI notification */
                struct TpUIEventInfo {
                    TpAddress OriginatingAddress; /* Address of the end-user for which notification shall be handled */
                    TpAddress DestinationAddress;
                    TpString ServiceCode; /* 2 digit code indicating the UI to be triggered. */
                    TpUIEventInfoDataType DataTypeIndication;
                    TpString DataString;
                };
            }
        }
    }
}
```

```

/* Defines the cause of the UI fault detected. */
enum TpUIFault {
    P_UI_FAULT_UNDEFINED, /* Undefined */
    P_UI_CALL_DEASSIGNED /* The related Call object has been deassigned. */
};

/* Defines the type of information send to the end-user */
enum TpUIInfoType {
    P_UI_INFO_ID, /* The information consists of an ID */
    P_UI_INFO_DATA, /* The information consists of a data string */
    P_UI_INFO_ADDRESS /* The information consists of a URL. */
};

/* Defines the Tagged Choice of Data Elements that specifies the information to be send to a end-user. */
union TpUIInfo switch(TpUIInfoType) {
    case P_UI_INFO_ID: TpInt32 InfoID; /*Defines the ID of the user information script or stream to send to an end-user.*/
    case P_UI_INFO_DATA: TpString IconData; /*Defines the data to be sent to an end-user's terminal.*/
    case P_UI_INFO_ADDRESS: TpURL InfoAddress; /*Defines the URL of the text or stream to be sent to an end-user's terminal*/
};

/* Defines the criteria for recording of messages */
struct TpUIMessageCriteria {
    TpString EndSequence; /* Defines the character(s) which terminate an input of variable length.
    */
    TpDuration MaxMessageTime; /* Specifies the maximum allowed duration in seconds. */
    TpInt32 MaxMessageSize; /* Specifies the maximum allowed size in bytes of the message. */
};

/* Defines the UI call reports if a response was requested. */
enum TpUIReport {
    P_UI_REPORT_UNDEFINED, /* Undefined report */
    P_UI_REPORT_ANNOUNCEMENT_ENDED, /* Confirmation that the announcement has ended */
    P_UI_REPORT_LEGAL_INPUT, /* Information collected., meeting the specified criteria. */
    P_UI_REPORT_NO_INPUT, /* User immediately entered the delimiter character. No valid information has been returned */
    P_UI_REPORT_TIMEOUT, /* User did not input any response before the input timeout expired */
    P_UI_REPORT_MESSAGE_STORED, /* A message has been stored successfully */
    P_UI_REPORT_MESSAGE_NOT_STORED /* The message has not been stored successfully */
};

/* Defines the situations for which a response is expected following the user interaction. */
const TpInt32 P_UI_RESPONSE_REQUIRED = 1; /* A response must be sent when the request has completed. */
const TpInt32 P_UI_LAST_ANNOUNCEMENT_IN_A_ROW = 2; /* This is the final announcement within a sequence. */
const TpInt32 P_UI_FINAL_REQUEST = 4; /* This is the final request. */

typedef TpInt32 TpUIResponseRequest; /* Defines the situations for which a response is expected following the user interaction. */

/* Defines the type of the variable parts in the information to send to the user. */
enum TpUIVariablePartType {
    P_UI_VARIABLE_PART_INT, /* Variable part is of type integer */
    P_UI_VARIABLE_PART_ADDRESS, /* Variable part is of type address */
    P_UI_VARIABLE_PART_TIME, /* Variable part is of type time */
    P_UI_VARIABLE_PART_DATE, /* Variable part is of type date */
    P_UI_VARIABLE_PART_PRICE /* Variable part is of type price */
};

/* Defines the Tagged Choice of Data Elements that specify the variable parts in the information to send to the user. */
union TpUIVariableInfo switch(TpUIVariablePartType) {
    case P_UI_VARIABLE_PART_INT: TpInt32 VariablePartInteger;
    case P_UI_VARIABLE_PART_ADDRESS: TpString VariablePartAddress;
    case P_UI_VARIABLE_PART_TIME: TpTime VariablePartTime;
    case P_UI_VARIABLE_PART_DATE: TpDate VariablePartDate;
    case P_UI_VARIABLE_PART_PRICE: TpPrice VariablePartPrice;
};

/* Defines a Numbered Set of Data Elements of TpUIVariableInfo. */
typedef sequence <TpUIVariableInfo> TpUIVariableInfoSet;

```

```

/* Define the possible Exceptions. */
exception TpGUISEException {
    TpInt32 exceptionType;
};

const TpInt32 P_GUIS_INVALID_CRITERIA = 768;           /* Invalid criteria specified */
const TpInt32 P_GUIS_ILLEGAL_ID = 769;                /* Information id specified is invalid */
const TpInt32 P_GUIS_ID_NOT_FOUND = 770;              /* Information id is not known to the User
   Interaction Service */
const TpInt32 P_GUIS_ILLEGAL_RANGE = 771;             /* The values for minimum and maximum
   collection length are out of range */
const TpInt32 P_GUIS_INVALID_COLLECTION_CRITERIA = 772; /* Invalid collection criteria specified */
const TpInt32 P_GUIS_INVALID_NETWORK_STATE = 774;       /* Although the sequence of method calls is
   allowed by the gateway, the underlying protocol can not support it. */
const TpInt32 P_GUIS_UNEXPECTED_SEQUENCE = 775;         /* Although the sequence of method calls is
   allowed by the gateway, the underlying protocol can not support it. */

}; // end module ui
}; // end module osa
}; // end module threegpp
}; // end module org

#endif

// END file UI.idl

```

## 9.4.2 Generic User Interaction IDL

```

// source file: GUI.idl
// GUIS Interface description

#ifndef __OSA_UI_GUI_DEFINED
#define __OSA_UI_GUI_DEFINED

#include <UI.idl>
#include <ECC.idl>

module org {
    module threegpp {
        module osa {
            module ui {
                module gui {

interface IpAppUIManager; // forward definition;
interface IpAppUI;          // forward definition;
interface IpAppUICall;      // forward definition;

/* The Generic User Interaction SCF Interface provides functions to send
   information to, or gather information from the user. */
interface IpUI : IpService {
    /* This method plays an announcement or sends other information to the user.*/
    void sendInfoReq (
        in TpSessionID userInteractionSessionID,
        in TpUIInfo info,
        in TpUIVariableInfoSet variableInfo,
        in TpInt32 repeatIndicator,
        in TpUIResponseRequest responseRequested,
        out TpAssignmentID assignmentID
    )
    raises (TpGUISEException, TpGeneralException);

    /* This method plays an announcement or sends other information to the user
       and collects some information from the user. */
    void sendInfoAndCollectReq (
        in TpSessionID userInteractionSessionID,
        in TpUIInfo info,
        in TpUIVariableInfoSet variableInfo,
        in TpUICollectCriteria criteria,
        in TpUIResponseRequest responseRequested,
        out TpAssignmentID assignmentID
    )
    raises (TpGUISEException, TpGeneralException);

    /* This method requests that the relationship between the application and
       the user interaction object be released. */
    void release (

```

```

        in TpSessionID userInteractionSessionID
    )
    raises (TpGUISEException, TpGeneralException);

};

/* Defines the Sequence of Data Elements that unambiguously specify the UI object */
struct TpUIIdentifier {
    TpSessionID UserInteractionSessionID;
    IpUI UIRef;
};

/* The Call User Interaction Service Interface provides functions to send
   information to, or gather information from, the user. */
interface IpUICall : IpUI {
    /* This asynchronous method aborts the specified user interaction operation. */
    void abortActionReq (
        in TpSessionID userInteractionSessionID,
        in TpAssignmentID assignmentID
    )
    raises (TpGUISEException, TpGeneralException);
};

/* Defines the Sequence of Data Elements that unambiguously specify the UICall object. */
struct TpUICallIdentifier {
    IpUICall UICallRef;
    TpSessionID UserInteractionSessionID;
};

/* This interface is the 'SCF manager' interface for the Generic User Interaction SCF. */
interface IpUIManager : IpService {
    /* This method is used to create a new user interaction object for non-call related purposes */
    void createUI (
        in IpAppUI appUI,
        in TpAddress userAddress,
        out TpUIIdentifier userInteraction
    )
    raises (TpGUISEException, TpGeneralException);

    /* This method is used to create a new user interaction object for call related purposes. */
    void createUICall (
        in IpAppUICall appUI,
        in org::threegpp::osa::cc::gcc::TpCallIdentifier callIdentifier,
        in org::threegpp::osa::cc::ecc::TpCallLegIdentifier callLegIdentifier,
        out TpUICallIdentifier userInteraction
    )
    raises (TpGUISEException, TpGeneralException);

    /* This method is used to enable the reception of user initiated user interaction. */
    void enableUINotification (
        in IpAppUIManager appInterface,
        in TpUIEventCriteria eventCriteria,
        out TpAssignmentID assignmentID
    )
    raises (TpGUISEException, TpGeneralException);

    /* This method is used by the application to disable UI notifications. */
    void disableUINotification (
        in TpAssignmentID assignmentID
    )
    raises (TpGUISEException, TpGeneralException);
};

/* The Generic User Interaction SCF manager application interface provides
   the application call management functions to the Generic User Interaction SCF. */
interface IpAppUIManager : IpOsa {
    /* This method indicates to the application that the User Interaction SCF
       instance has terminated or closed abnormally. */
    void userInteractionAborted (
        in TpUIIdentifier userInteraction
    )
    raises (TpGUISEException, TpGeneralException);

    /* This method notifies the application of an user initiated request for user interaction. */
    void userInteractionEventNotify (
        in TpUIIdentifier ui,

```

```

    in TpUIEventInfo eventInfo,
    in TpAssignmentID assignmentID,
    out IpAppUI appInterface
)
raises (TpGUISEException, TpGeneralException);

void userInteractionNotificationInterrupted ()
raises (TpGUISEException, TpGeneralException);

void userInteractionNotificationContinued ()
raises (TpGUISEException, TpGeneralException);

};

/* The User Interaction Application Interface is used to handle generic user
   interaction request responses and reports. */
interface IpAppUI : IpOsa {
    /* This method informs the application about the start or the completion of a sendInfoCallReq().
       */
    void sendInfoRes (
        in TpSessionID userInteractionSessionID,
        in TpAssignmentID assignmentID,
        in TpUIReport response
)
raises (TpGUISEException, TpGeneralException);

/* This asynchronous method indicates that the request to send information was unsuccessful. */
void sendInfoErr (
    in TpSessionID userInteractionSessionID,
    in TpAssignmentID assignmentID,
    in TpUIError error
)
raises (TpGUISEException, TpGeneralException);

/* This asynchronous method returns the information collected to the application. */
void sendInfoAndCollectRes (
    in TpSessionID userInteractionSessionID,
    in TpAssignmentID assignmentID,
    in TpUIReport response,
    in TpString info
)
raises (TpGUISEException, TpGeneralException);

/* This asynchronous method indicates that the request to send information
   and collect a response was unsuccessful. */
void sendInfoAndCollectErr (
    in TpSessionID userInteractionSessionID,
    in TpAssignmentID assignmentID,
    in TpUIError error
)
raises (TpGUISEException, TpGeneralException);

/* This method indicates to the application that a fault has been detected in the user
   interaction. */
void userInteractionFaultDetected (
    in TpSessionID userInteractionSessionID,
    in TpUIFault fault
)
raises (TpGUISEException, TpGeneralException);
};

/* The Call User Interaction Application Interface is used to handle call user
   interaction request responses and reports. */
interface IpAppUICall : IpAppUI {
    /* This method confirms that the request to abort a user interaction operation on a call was
       successful. */
    void abortActionRes (
        in TpSessionID userInteractionSessionID,
        in TpAssignmentID assignmentID
)
raises (TpGUISEException, TpGeneralException);

/* This asynchronous method indicates that the request to abort a user interaction
   operation on a call resulted in an error.*/
void abortActionErr (
    in TpSessionID userInteractionSessionID,
    in TpAssignmentID assignmentID,

```



## 9.5 Data Session Control

```
// OSA data session control

#ifndef __OSA_DSC_DEFINED
#define __OSA_DSC_DEFINED

#include "osa.idl"

module org
{
    module threegpp
    {
        module osa
        {

            // data session control
            module dsc
            {

                interface IpDataSessionControlManager; // forward definition
                interface IpDataSession; // forward definition
                interface IpAppDataSessionControlManager; // forward definition
                interface IpAppDataSession; // forward definition

                const TpInt32 P_EVENT_NAME_UNDEFINED = 0; // Undefined
                const TpInt32 P_EVENT_DSCS_ESTABLISHED_ = 1; // Data Session established

                typedef TpInt32 TpDataSessionEventName; /*Defines the names of event being notified. */

                enum TpDataSessionChargeOrderCategory
                {
                    P_DATA_SESSION_CHARGE_PER_VOLUME,
                    P_DATA_SESSION_CHARGE_NETWORK
                };

                struct TpChargePerVolume
                {
                    TpInt32 InitialCharge;
                    TpInt32 CurrentChargePerKilobyte;
                    TpInt32 NextChargePerKilobyte;
                };

                union TpDataSessionChargeOrder switch(TpDataSessionChargeOrderCategory)
                {
                    case P_DATA_SESSION_CHARGE_PER_VOLUME: TpChargePerVolume ChargePerVolume;
                    case P_DATA_SESSION_CHARGE_NETWORK: TpString NetworkCharge;
                };

                struct TpDataSessionChargePlan
                {
                    TpDataSessionChargeOrder ChargeOrderType;
                    TpString Currency;
                    TpString AdditionalInfo;
                };

                struct TpDataSessionEventCriteria
                {
                    TpAddressRange DestinationAddress; /*Destination address range*/
                    TpAddressRange OriginationAddress; /*Origination address range */
                    TpDataSessionEventName DataSessionEventName; /*Name of the event(s) */
                };

                /* Defines the mode that the data session will monitor for events, or the mode that the
                data session is in following a detected event. */
                enum TpDataSessionMonitorMode
                {
                    P_DATA_SESSION_MONITOR_MODE_INTERRUPT, /* The data session event is intercepted by
                    the data session control SCF and data session establishment is interrupted. The application
                };
            };
        };
    };
};

/* The data session event is interrupted by
the data session control SCF and data session establishment is interrupted. The application
*/
```

```

is notified of the event and data session establishment resumes following an appropriate API
call or network event (such as a data session release) */
    P_DATA_SESSION_MONITOR_MODE_NOTIFY,           /* The data session event is detected by the
data session control SCF but not intercepted. The application is notified of the event data
session establishment continues */
    P_DATA_SESSION_MONITOR_MODE_DO_NOT_MONITOR /* Do not monitor for the event */
};

struct TpDataSessionEventInfo
{
    TpAddress DestinationAddress;
    TpAddress OriginatingAddress;
    TpDataSessionEventName DataSessionEventName;
    TpDataSessionMonitorMode MonitorMode;
};

/* Defines the Sequence of Data Elements that specify the cause of the release of a
call.*/
struct TpDataSessionReleaseCause
{
    TInt32 Value;
    TInt32 Location;
};

/* Defines a specific data session error. */
enum TpDataSessionErrorType
{
    P_DATA_SESSION_ERROR_UNDEFINED,      /* Undefined */
    P_DATA_SESSION_ERROR_INVALID_ADDRESS, /* The operation failed because an invalid
address was given */
    P_DATA_SESSION_ERROR_INVALID_STATE   /* The data session was not in a valid state for
the requested operation */
};

/* Defines the Tagged Choice of Data Elements that specify additional data session error
and data session error specific information. */
union TpDataSessionAdditionalErrorInfo switch(TpDataSessionErrorType)
{
    case P_DATA_SESSION_ERROR_INVALID_ADDRESS: TpAddressError
DataSessionErrorInvalidAddress;
};

/* Defines the Sequence of Data Elements that specify the additional information
relating to an undefined data session error. */
struct TpDataSessionError
{
    TpDataSessionAdditionalErrorInfo AdditionalErrorInfo;
    TpDataSessionErrorType ErrorType;
    TpDateAndTime ErrorTime;
};

/* Defines the cause of the Data Session fault detected. */
enum TpDataSessionFault
{
    P_DATA_SESSION_FAULT_UNDEFINED,      /* Undefined */
    P_DATA_SESSION_FAULT_USER_ABORTED,  /* User has finalised the data session before any
message could be sent by the application. */
    P_DATA_SESSION_TIMEOUT_ON_RELEASE,  /* Final report has been sent to the application,
but the application did not explicitly release data session object, within a specified time.
*/
    P_DATA_SESSION_TIMEOUT_ON_INTERRUPT /* Application did not instruct the gateway how to
handle the data session within a specified time, after the gateway reported an event that was
requested by the application in interrupt mode.*/
};

/* Defines a specific data session event report type. */
enum TpDataSessionReportType
{
    P_DATA_SESSION_REPORT_UNDEFINED,      /* Undefined */
    P_DATA_SESSION_REPORT_CONNECTED,     /* Data session established */
    P_DATA_SESSION_REPORT_DISCONNECT    /* data session disconnect requested by data
session party */
};

/* Defines the Tagged Choice of Data Elements that specify additional data session report
information. */
union TpDataSessionAdditionalReportInfo switch(TpDataSessionReportType)

```

```

{
    case P_DATA_SESSION_REPORT_DISCONNECT: TpDataSessionReleaseCause DataSessionDisconnect;
};

struct TpDataSessionReport
{
    TpDataSessionMonitorMode MonitorMode;
    TpDateAndTime DataSessionEventTime;
    TpDataSessionReportType DataSessionReportType;
    TpDataSessionAdditionalReportInfo AdditionalReportInfo;
};

/* Defines the Sequence of Data Elements that specify the criteria relating to Data
Session report requests.*/
struct TpDataSessionReportRequest
{
    TpDataSessionMonitorMode MonitorMode;
    TpDataSessionReportType DataSessionReportType;
};

/* Defines a Numbered Set of Data Elements of TpDataSessionReportRequest.*/
typedef sequence <TpDataSessionReportRequest> TpDataSessionReportRequestSet;

const TInt32 P_DATA_SESSION_SUPERVISE_VOLUME_REACHED = 1; /* The Data Session
supervision volume has been reached.*/
const TInt32 P_DATA_SESSION_SUPERVISE_DATA_SESSION_ENDED = 2; /* The data session has
ended, either due to reach of maximum volume or calling or called party release.*/
const TInt32 P_DATA_SESSION_SUPERVISE_MESSAGE_SENT = 4; /* A warning message has been
sent. */

/* Defines the responses from the data session control SCF for data sessions that are
supervised:*/
typedef TInt32 TpDataSessionSuperviseReport;

const TInt32 P_DATA_SESSION_SUPERVISE_RELEASE = 1; /* Release the Data Session when
the Data Session supervision volume has been reached.*/
const TInt32 P_DATA_SESSION_SUPERVISE RESPOND = 2; /* Notify the application when the
data session supervision volume has been reached.*/
const TInt32 P_DATA_SESSION_SUPERVISE_INFORM = 4; /* Send a warning message to the
originating party when the maximum volume is reached. If data session release is requested,
then the data session will be released following the message after an administered time
period */
/* Defines the following treatment of the data session by the data session control SCF when
the maximum volume has been reached.*/
typedef TInt32 TpDataSessionSuperviseTreatment;

/* Defines the Sequence of Data Elements that specify the amount of volume that is allowed
to be transmitted for the specific connection.*/
struct TpDataSessionSuperviseVolume {
    TInt32 VolumeQuantity; /* Quantity of the granted volume that can be transmitted for the
specific connection.*/
    TInt32 VolumeUnit; /* Unit of the granted volume that can be transmitted for the
specific connection.*/
};

/* Define the possible Exceptions.*/
const TInt32 P_DSCS_SERVICE_INFORMATION_MISSING = 1024;
const TInt32 P_DSCS_SERVICE_FAULT_ENCOUNTERED = 1025;
const TInt32 P_DSCS_UNEXPECTED_SEQUENCE = 1026;
const TInt32 P_DSCS_INVALID_ADDRESS = 1027;
const TInt32 P_DSCS_INVALID_STATE = 1028;
const TInt32 P_DSCS_INVALID_CRITERIA = 1029;
const TInt32 P_DSCS_INVALID_NETWORK_STATE = 1030;

exception TpDSCSException
{
    TInt32 exceptionType;
};

/* Sequence of Data Elements that unambiguously specify the Data Session object */
struct TpDataSessionIdentifier
{
    IpDataSession DataSessionReference;
    TpSessionID DataSessionSessionID;
};

```

```

/* This interface is the SCF manager' interface for Data Session Control. */
interface IpDataSessionControlManager : IpService
{
    /* This method is used to enable data session notifications. */
    void enableDataSessionNotification (
        in IpAppDataSessionControlManager appInterface,
        in TpDataSessionEventCriteria eventCriteria,
        out TpAssignmentID assignmentID)
        raises (TpDSCSEException, TpGeneralException);

    /* This method is used by the application to disable data session notifications.*/
    void disableDataSessionNotification
    (
        in TpAssignmentID assignmentID)
        raises (TpDSCSEException, TpGeneralException);
};

/* This interface provides the means to control a data session. */
interface IpDataSession : IpService
{
    /* This method requests connection of the data session to the destination party.*/
    void connectReq (
        in TpSessionID dataSessionID,
        in TpDataSessionReportRequestSet responseRequested,
        in TpAddress targetAddress,
        in TpAddress originatingAddress,
        out TpAssignmentID assignmentID)
        raises (TpDSCSEException, TpGeneralException);

    /* This method requests the release of the data session and associated objects.*/
    void release (
        in TpSessionID dataSessionID,
        in TpDataSessionReleaseCause cause)
        raises (TpDSCSEException, TpGeneralException);

    /* The application calls this method to supervise a data session. */
    void superviseDataSessionReq (
        in TpSessionID dataSessionID,
        in TpDataSessionSuperviseTreatment treatment,
        in TpDataSessionSuperviseVolume bytes)
        raises (TpDSCSEException, TpGeneralException);

    /* The application calls this method to set the charge plan */
    void setDataSessionChargePlan (
        in TpSessionID dataSessionID,
        in TpDataSessionChargePlan dataSessionChargePlan)
        raises (TpDSCSEException, TpGeneralException);

    /* The application calls this method to send advice of charge information */
    void setAdviceOfCharge (
        in TpSessionID dataSessionID,
        in TpAoCInfo aoCInfo,
        in TpDuration tariffSwitch)
        raises (TpDSCSEException, TpGeneralException);
};

/* The data session control manager application interface provides the
application data session control management functions to the data session control
SCF. */
interface IpAppDataSessionControlManager : IpOsa
{
    void dataSessionAborted (
        in TpSessionID dataSessionReference)
        raises (TpDSCSEException, TpGeneralException);

    /* This method notifies the application of the arrival of a data session-related event.
*/
    void dataSessionEventNotify (
        in TpDataSessionIdentifier dataSessionReference,

```

```

        in TpDataSessionEventInfo eventInfo,
        in TpAssignmentID assignmentID,
        out IpAppDataSession appInterface)
    raises (TpDSCSEException, TpGeneralException);

    /* This method indicates to the application that all event notifications
     * are resumed.*/
    void dataSessionNotificationContinued()
        raises (TpDSCSEException, TpGeneralException);

    /* This method indicates to the application that all event notifications
     * are temporarily interrupted.*/
    void dataSessionNotificationInterrupted()
        raises (TpDSCSEException, TpGeneralException);

};

/* The application side of the data session interface is used to handle data session
request responses and state reports. */
interface IpAppDataSession : IpOsa
{
    /* This method indicates that the request to route the data session to the
destination was successful.*/
    void connectRes (
        in TpSessionID dataSessionSessionID,
        in TpDataSessionReport eventReport,
        in TpAssignmentID assignmentID)
    raises (TpDSCSEException, TpGeneralException);

    /* This method indicates that the request to connect the data session to the
destination party was unsuccessful. */
    void connectErr (
        in TpSessionID dataSessionSessionID,
        in TpDataSessionError errorIndication,
        in TpAssignmentID assignmentID)
    raises (TpDSCSEException, TpGeneralException);

    /* This asynchronous method reports a data session supervision event to the
application.*/
    void superviseDataSessionRes (
        in TpSessionID dataSessionSessionID,
        in TpDataSessionSuperviseReport report,
        in TpDataSessionSuperviseVolume usedVolume)
    raises (TpDSCSEException, TpGeneralException);

    /* This asynchronous method reports a data session supervision error to the
application.*/
    void superviseDataSessionErr (
        in TpSessionID dataSessionSessionID,
        in TpDataSessionError errorIndication)
    raises (TpDSCSEException, TpGeneralException);

    /* This method indicates to the application that a fault in the network has
been detected.*/
    void dataSessionFaultDetected (
        in TpSessionID dataSessionSessionID,
        in TpDataSessionFault fault)
    raises (TpDSCSEException, TpGeneralException);

};

};

// end module dsc
////////////////////////////////////////////////////////////////
};

// osa
}; // threegpp
};

#endif

```

## 9.6 Network User Location and User Status IDL

### 9.6.1 Common definitions for Network User Location and User Status: MM.idl

```
#include <OSA.idl>

module org {
    module threegpp {
        module osa {
            module mm {

                // Defines the type of uncertainty shape.

                enum TpLocationUncertaintyShape {
                    P_M_SHAPE_NONE,      // No uncertainty shape present.
                    P_M_SHAPE_CIRCLE,   // Uncertainty shape is a circle.
                    P_M_SHAPEa_CIRCLE_SECTOR, // Uncertainty shape is a circle sector.
                    P_M_SHAPE_CIRCLE_ARC_STRIPE, // Uncertainty shape is a circle arc stripe.
                    P_M_SHAPE_ELLIPSE,       // Uncertainty shape is an ellipse.
                    P_M_SHAPE_ELLIPSE_SECTOR, // Uncertainty shape is an ellipse sector.
                    P_M_SHAPE_ELLIPSE_ARC_STRIPE // Uncertainty shape is an ellipse arc stripe.
                };

                // Defines the structure of data elements that specify a geographical position.

                // An "ellipsoid point with uncertainty shape" defines the horizontal location.
                // The reference system chosen for the coding of locations is the World Geodetic
                // System 1984 (WGS 84).

                struct TpGeographicalPosition {
                    TpFloat Longitude;
                    TpFloat Latitude;
                    TpLocationUncertaintyShape TypeOfUncertaintyShape;
                    TpFloat UncertaintyInnerSemiMajor;
                    TpFloat UncertaintyOuterSemiMajor;
                    TpFloat UncertaintyInnerSemiMinor;
                    TpFloat UncertaintyOuterSemiMinor;
                    TpInt32 AngleOfSemiMajor;
                    TpInt32 SegmentStartAngle;
                    TpInt32 SegmentEndAngle;
                };
            }
        }
    }
}
```

```

// Defines a diagnostic value that is reported in addition to an error by
// the Network User Location or User Status SCFs.

enum TpMobilityDiagnostic {
    P_M_NO_INFORMATION,           // No diagnostic information present.
                                // Valid for all type of errors.

    P_M_APPL_NOT_IN_PRIV_EXCEPT_LST, // Application not in privacy exception list.
                                // Valid for 'Unauthorised Application' error.

    P_M_CALL_TO_USER_NOT_SETUP,    // Call to user not set-up. Valid for
                                // 'Unauthorised Application' error.

    P_M_PRIVACY_OVERRIDE_NOT_APPLIC, // Privacy override not applicable. Valid for
                                // 'Unauthorised Application' error.

    P_M_DISALL_BY_LOCAL_REGULAT_REQ, // Disallowed by local regulatory requirements.
                                // Valid for 'Unauthorised Application' error.

    P_M_CONGESTION,              // Congestion. Valid for 'Position Method
                                // Failure' error.

    P_M_INSUFFICIENT_RESOURCES,   // Insufficient resources. Valid for 'Position
                                // Method Failure' error.

    P_M_INSUFFICIENT_MEAS_DATA,   // Insufficient measurement data. Valid for
                                // 'Position Method Failure' error.

    P_M_INCONSISTENT_MEAS_DATA,   // Inconsistent measurement data. Valid for
                                // 'Position Method Failure' error.

    P_M_LOC_PROC_NOT_COMPLETED,    // Location procedure not completed. Valid for
                                // 'Position Method Failure' error.

    P_M_LOC_PROC_NOT_SUPP_BY_USER, // Location procedure not supported by user.
                                // Valid for 'Position Method Failure' error.

    P_M_QOS_NOT_ATTAINABLE // Quality of service not attainable. Valid for
                                // 'Position Method Failure' error.

};

// Defines an error that is reported by the Network User Location or User Status SCFs.

enum TpMobilityError {
    P_M_OK,                     // No error occurred while processing the request.

    P_M_SYSTEM_FAILURE,          // System failure. The request can not be handled because
                                // of a general problem in the network user location SCF
                                // , the user status SCFor the
                                // underlying network. Fatal
}

```

```

P_M_UNAUTHORIZED_NETWORK, // Unauthorised network. The requesting network is
                         // not authorised to obtain the user's location or
                         // status. Non fatal

P_M_UNAUTHORIZED_APPLICATION, // Unauthorised application. The application is
                             // not authorised to obtain the user's location
                             // or status. Fatal

P_M_UNKNOWN_SUBSCRIBER, // Unknown subscriber. The user is unknown, i.e. no
                        // such subscription exists. Fatal

P_M_ABSENT_SUBSCRIBER, // Absent subscriber. The user is currently not
                        // reachable. Non fatal

P_M_POSITION_METHOD_FAILURE // Position method failure. The network user location SCF
                            // failed to obtain the user's position. Non fatal

};

// This enumeration is used in requests to stop network user location or user status
// reports that are

// sent from a network user location or user status SCFs to an application.

enum TpMobilityStopScope {
    P_M_ALL_IN_ASSIGNMENT, // The request concerns all users in an assignment.

    P_M_SPECIFIED_USERS   // The request concerns only the users that are
                          // explicitly specified in a collection.

};

// Defines the structure of data element that specifies a request to stop whole or parts of an
// assignment. Assignments are used for periodic or triggered reporting of a
// user locations or statuses. Observe that the parameter 'Users' is optional.
// If the parameter 'stopScope' is set to P_M_ALL_IN_ASSIGNMENT, the parameter
// 'stopScope' is undefined. If the parameter stopScope is set to
// P_M_SPECIFIED_USERS, then the assignment shall be stopped only for the users
// specified in the 'users' collection.

struct TpMobilityStopAssignmentData {
    // Identity of the session that shall be stopped.

    TpSessionID          AssignmentId;

    // Specify if only a part of the assignment or if whole the assignment
    // shall be stopped.

    TpMobilityStopScope StopScope;

    // Optional parameter describing which users a stop request is
    // addressing when only a part of an assignment is to be stopped.

    TpAddressSet         Users;

};

```

```
}; }; };
```

## 9.6.2 Network User Location: MMul.idl

```
/************************************************************************/
// Data Definitions & Interfaces
// Network User Location
/************************************************************************/

#include <MM.idl>

module org {
    module threegpp {
        module osa {
            module mm {
                module ul {

                    /************************************************************************/
                    // Data definitions
                    /************************************************************************/

                    // This data type is identical to a TString. It specifies the Cell Global
                    // Identification or the Location Area Identification (LAI).

                    // The Cell Global Identification (CGI) is defined as the string of characters
                    // in the following format:
                    //      MCC-MNC-LAC-CI
                    // where:
                    //      MCC   Mobile Country Code (three decimal digits)
                    //      MNC   Mobile Network Code (two or three decimal digits)
                    //      LAC   Location area code (four hexadecimal digits)
                    //      CI    Cell Identification (four hexadecimal digits)
                    //

                    // The Location Area Identification (LAI) is defined as a string of characters
                    // in the following format:
                    //      MCC-MNC-LAC
                    // where:
                    //      MCC   Mobile Country Code (three decimal digits)
                    //      MNC   Mobile Network Code (two or three decimal digits)
                    //      LAC   Location area code (four hexadecimal digits)
                    //

                    // The length of the parameter indicates which format is used. See 3G TS 29.002 for
                }
            }
        }
    }
}
```

```

// the detailed coding.

typedef TpString TpLocationCellIDOrLAI;

// Defines the structure of data elements that specifies the criteria for a
// triggered location report to be generated.

struct TpLocationTriggerCamel {

    TpBoolean UpdateInsideVlr; // Generate location report when it occurs an
                                // location update inside the current VLR area.

    TpBoolean UpdateOutsideVlr; // Generate location report when the user moves
                                // to another VLR area.

};

// Defines the structure of data elements that specifies the location of a mobile
// telephony user. Observe that if the StatusCode is indicating an error ,
// then neither GeographicalPosition, Timestamp, VlrNumber, LocationNumber,
// CellIdOrLai nor their associated presense flags are defined.

struct TpUserLocationCamel {

    TpAddress UserID;      // The address of the user.

    TpMobilityError StatusCode; // Indicator of error.

    TpBoolean GeographicalPositionPresent; // Flag indicating if the
                                            // geographical position is present.

    TpGeographicalPosition GeographicalPosition; // Specification of a position
                                                // and an area of uncertainty.

    TpBoolean TimestampPresent; // Flag indicating if the timestamp is present.

    TpDateAndTime Timestamp;      // Timestamp indicating when the location information// was attained

    TpBoolean VlrNumberPresent; // Flag indicating if the VLR number is present.

    TpAddress VlrNumber;        // Current VLR number for the user.

    TpBoolean LocationNumberPresent; // Flag indicating if the location
                                    // number is present.

    TpAddress LocationNumber;    // Current location number.

    TpBoolean CellIdOrLaiPresent; // Flag indicating if cell-id or
                                // LAI of the user is present.

    TpLocationCellIDOrLAI CellIdOrLai; // Cell-id or LAI of the user.

};

typedef sequence <TpUserLocationCamel> TpUserLocationCamelSet;

/***********************/

//           Interface definitions

```

```
*****
interface IpAppUserLocationCamel; // Forward definition

// Inherits from the generic service capability feature interface.

// This interface is the SCF manager's interface for Network User Location.

interface IpUserLocationCamel : IpService {

    // Request for mobile-related location information on one or several wireless users.

    void locationReportReq(
        in IpAppUserLocationCamel appLocationCamel,
        in TpAddressSet           users,
        out TpSessionID          assignmentId)
        raises (TpGeneralException);

    // Request for periodic mobile location reports on one or several users.

    void periodicLocationReportingStartReq(
        in IpAppUserLocationCamel appLocationCamel,
        in TpAddressSet           users,
        in TpDuration             reportingInterval,
        out TpSessionID          assignmentId)
        raises (TpGeneralException);

    // This method stops the sending of periodic mobile location reports for
    // one or several users.

    void periodicLocationReportingStop(
        in TpMobilityStopAssignmentData stopRequest)
        raises (TpGeneralException);

    // Request for user location reports, containing mobile related information,
    // when the location is changed (the report is triggered by the location change).

    void triggeredLocationReportingStartReq(
        in IpAppUserLocationCamel appLocationCamel,
        in TpAddressSet           users,
        in TpLocationTriggerCamel trigger,
        out TpSessionID          assignmentId)
        raises (TpGeneralException);

    // Request that triggered mobile location reporting should stop.

    void triggeredLocationReportingStop()
```

```
    in TpMobilityStopAssignmentData stopRequest)
        raises (TpGeneralException);
};

// Inherits from the generic service capability feature interface.

// The network user location application interface is implemented by the client
// application developer and is used to handle location reports that are
// specific for mobile telephony users.

interface IpAppUserLocationCamel : IpOsa {

    // Delivery of a mobile location report. The report is containing
    // mobile-related location information for one or several users.

    void locationReportRes(
        in TpSessionID           assignmentId,
        in TpUserLocationCamelSet locations)
            raises (TpGeneralException);

    // This method indicates that the location report request has failed.

    void locationReportErr(
        in TpSessionID           assignmentId,
        in TpMobilityError        cause,
        in TpMobilityDiagnostic   diagnostic);

    // Periodic delivery of mobile location reports. The reports are
    // containing mobile-related location information for one or several users.

    void periodicLocationReport(
        in TpSessionID           assignmentId,
        in TpUserLocationCamelSet locations)
            raises (TpGeneralException);

    // This method indicates that a requested periodic location report has
    // failed. Note that errors only concerning individual users are reported
    // in the ordinary periodicLocationReport() message.

    void periodicLocationReportErr(
        in TpSessionID           assignmentId,
        in TpMobilityError        cause,
        in TpMobilityDiagnostic   diagnostic);

    // Delivery of a report that is indicating that one or several user's
    // mobile location has changed.
```

```

void triggeredLocationReport(
    in TpSessionID           assignmentID,
    in TpUserLocationCamel   location,
    in TpLocationTriggerCamel criterion)
    raises (TpGeneralException);

// This method indicates that a requested triggered location report has
// failed. Note that errors only concerning individual users are reported
// in the ordinary triggeredLocationReport() message.

void triggeredLocationReportErr(
    in TpSessionID           assignmentID,
    in TpMobilityError        cause,
    in TpMobilityDiagnostic   diagnostic);
};

} ; } ; } ; } ; }

} ; } ; } ; } ; }
```

### 9.6.3 User Status: MMus.idl

```

***** Data Definitions & Interfaces *****

// User Status

***** Data Definitions *****

#include <MM.idl>

module org {
    module threegpp {
        module osa {
            module mm {
                module us {

***** Data definitions *****

                    // Defines the status of a user.

enum TpUserStatusIndicator {
    P_US_REACHABLE,      // User is reachable
    P_US_NOT_REACHABLE, // User is not reachable
    P_US_BUSY            // User is busy (only applicable for interactive user
}
```

```

        // status request, not when triggers are used)
};

// Defines the structure of data elements that specify the identity
// and status of a user.

struct TpUserStatus {
    TpAddress          UserID;      // The user address.
    TpMobilityError    StatusCode;   // Indicator of error.
    TpUserStatusIndicator Status;    // The current status of the user.
};

typedef sequence <TpUserStatus> TpUserStatusSet;

/*****************
// Interface definitions
*****************/

interface IpAppUserStatus; // Forward definition

// Inherits from the generic service capability feature interface.

// The user status interface represents the interface to the user status SCF.

interface IpUserStatus : IpService {

    // Request for a report on the status of one or several users.

    void statusReportReq(
        in  IpAppUserStatus    appStatus,
        in  TpAddressSet       users,
        out TpSessionID        assignmentId)
            raises (TpGeneralException);

    // Request for triggered status reports when one or several user's
    // status is changed. The user status SCF will send a report when
    // the status changes.

    void triggeredStatusReportingStartReq (
        in  IpAppUserStatus    appStatus,
        in  TpAddressSet       users,
        out TpSessionID        assignmentId)
            raises (TpGeneralException);

    // This method stops the sending of status reports for one or several users.
}

```

```

void triggeredStatusReportingStop (
    in TpMobilityStopAssignmentData stopRequest)
    raises (TpGeneralException);

};

// Inherits from the base osa interface.

// The user-status application interface is implemented by the client
// application developer and is used to handle user status reports.

interface IpAppUserStatus : IpOsa {

    // Delivery of a report, that is containing one or several user's status.

    void statusReportRes(
        in TpSessionID      assignmentId,
        in TpUserStatusSet  status)
        raises (TpGeneralException);

    // This method indicates that the status report request has failed.

    void statusReportErr(
        in TpSessionID      assignmentId,
        in TpMobilityError   cause,
        in TpMobilityDiagnostic diagnostic);

    // Delivery of a report that is indicating that a user's status has changed.

    void triggeredStatusReport(
        in TpSessionID      assignmentId,
        in TpUserStatus      status)
        raises (TpGeneralException);

    // This method indicates that a requested triggered status reporting has
    // failed. Note that errors only concerning individual users are reported
    // in the ordinary triggeredStatusReport() message.

    void triggeredStatusReportErr(
        in TpSessionID      assignmentId,
        in TpMobilityError   cause,
        in TpMobilityDiagnostic diagnostic);
};

} ; } ; } ; } ; } ;

```

## 9.6.4 Terminal Capabilities: TERMCAP.idl

```

#ifndef __TERMCAP_DEFINED
#define __TERMCAP_DEFINED

#include <OSA.idl>

module org {
module threeGPP {
module osa {
module termcap {

enum TpTerminalCapabilitiesError {
    P_TERMCAP_ERROR_UNDEFINED,
    P_TERMCAP_INVALID_TERMINALID,
    P_TERMCAP_SYSTEM_FAILURE
        /* Undefined */
        /* Terminal ID not valid */
        /* General problem in terminal capabilities SCF or
        in underlying network */

};

exception TpTermCapException {
    TpTerminalCapabilitiesError error;
};

/* TpTerminalCapabilities: Structure containing status code and terminal
capabilities. */
struct TpTerminalCapabilities {
    /* statusCode: Indicates whether or not the terminalCapabilities
are available. */
    TpBoolean StatusCode;
    /* terminalCapabilities: Specifies the latest available capabilities of the user's terminal.
    This information, if available, is returned as CC/PP headers as specified in W3C [12] and
    adopted in the WAP UAProf specification [13]. It contains URLs; terminal attributes and
    values, in RDF format; or a combination of both. */
    TpString TerminalCapabilities;
};

interface IpTerminalCapabilities : IpService {
    /* Method: getTerminalCapabilities()
    This method is used by an application to get the capabilities of a
    user's terminal. Direction: Application to Network

    In parameter TerminalIdentity: Identifies the terminal. It may be
    a logical address known by the WAP Gateway/PushProxy.
    Out parameter, see TerminalCapabilityStruct*/
    void getTerminalCapabilities (
        in TpString terminalIdentity,
        out TpTerminalCapabilities result
    )
    raises (TpTermCapException, TpGeneralException);
};

};

};

};

#endif

```

---

## Annex A (informative): Change history

Change history							Old	New
Date	TSG #	TSG Doc.	CR	Rev	Subject/Comment			
June 2000	CN#08	NP-000310			Approval of Specification		2.0.0	3.0.0

---

## History

<b>Document history</b>		
V3.0.0	June 2000	Publication